

Simlab
COMPOSER 9.1
USER MANUAL



SimLab
SOFT

Composer 9.1

User Manual

Table of Contents

<i>Introduction</i>	5
About SimLab Composer.....	7
Icons Used in This Manual.....	9
What's New.....	11
<i>Composer GUI</i>	15
Workbench Icon.....	17
Specific Tools.....	19
Object Tree.....	20
Accessibility Toolbar.....	23
Navigator Panel.....	27
Materials Library.....	28
Libraries.....	32
Animation Library.....	39
Scene State Library.....	41
Sequence.....	42
Properties Panel.....	44
Smart Toolbar.....	53
Drag-and-Drop.....	55
Current Action Area.....	56
Camera Snapshot.....	57
Messages Area.....	59
View Cube.....	60
<i>Composer Workbenches</i>	61
Scene Building Workbench.....	62
File Menu.....	64
Move Menu.....	124
Create Menu.....	128
Geometry Menu.....	163
Material Menu.....	172
UV Menu.....	180
Scene States Menu.....	181
Render Menu.....	185
Image Effect Menu.....	202

Texture Baking Workbench.....	204
Baking Menu.....	206
Baking Tools Menu.....	208
Show Baked Menu.....	209
Animation Workbench.....	210
Object Menu	213
Camera Menu	220
Video Menu	223
Walk-through Menu	226
Animation Timeline.....	237
Animation Auto Ease Options.....	240
Sequence Timeline.....	246
Simulation Workbench	249
Solid Menu.....	252
Links Menu.....	265
Simulation Menu.....	275
Interactive Menu.....	283
Automation Workbench.....	291
Debugging Java Scripts.....	298
Visual Scripting	302
VR Workbench.....	307
Visual Effects Menu	309
Actions Menu	323
Light & Shadow Baking.....	344
360 Image.....	348
360s Grid Technology	356
Viewer Menu	359
VR/AR Mobile.....	397
Training Builder	402
VR Catalog Menu.....	411
<i>Keyboard Shortcuts.....</i>	<i>416</i>
<i>Contacts & Credits.....</i>	<i>418</i>
<i>Ordering and License</i>	<i>419</i>
<i>System Requirements.....</i>	<i>420</i>

Introduction

About SimLab Composer



Since the foundation of Simlab Soft, it's mission was clearly defined as developing state-of-the-art 3-D software that is affordable, fun and easy to use; represented in SimLab Composer with the vision in mind of making 3-D for all.

SimLab Composer is a 3-D Computer Graphics (CG) software for making images, animation and simulations. It was developed by Simulation Lab Software L.L.C.It is frequently used in video game development, TV commercial, architectural visualization, and engineering.

More precisely, SimLab Composer is an interior (indoor) and exterior (outdoor) 3-D scene building, sharing, rendering, baking, animation, automation, simulation, and exhibition application. It supports importing native and standard 3-D file formats to build scenes, that can be yet exported into many file formats.

SimLab Composer is built from multiple workbenches that match all your needs. The workbenches, developed so far, are Scene Building Workbench, Sharing Workbench, Rendering Workbench, Interior Workbench, Texture Baking Workbench, Animation Workbench, Simulation Workbench, Automation Workbench, and Exhibition Workbench. The GUI (Graphical User Interface) of SimLab Composer is designed to be very easy to use, which requires a short learning curve for exposing the application functionalities and capabilities.

With each new release of SimLab Composer, SimLab Soft aims to make their partners and clients around the world happier and more satisfied, though providing them by the right 3-D tools, helping to achieve their success fast and within budget. The latest version of SimLab Composer involves new features, in addition to enhancements and improvements to the previous features that are already included in the previous versions of SimLab Composer.

The manual is divided into two chapters, each of which is further divided into relevant topics. Each chapter relates to the most important concepts in SimLab Composer.

Icons Used in This Manual

To make your experience with the manual easier, you'll find a handful of icons at the left margin of the manual to indicate particular points of interest.



The Tip icon points out interesting techniques, helpful information, or hints that is likely to make your job easier.



The Remember icon is a friendly cue about things to keep in mind when performing certain tasks, or important information that can benefit you in understanding how SimLab Composer works.



Paragraphs marked with this icon include important information that will help you avoid common mistakes and steer clear of trouble.



Occasionally, we include some technical information that, while interesting to some, is not essential reading for everyone.



The on the web icon calls your attention to useful material that you can find online.



The example icon alerts you to some really cool examples illustrating techniques and issues.



The video icon alerts you to very useful tutorial and demo videos in our Youtube channel.



The Tutorial icon alerts you to very useful written tutorials.



The Script icon alerts you to very useful Scripting for Composer.

What's New

Features in SimLab Composer 9.1

A brief summary with regards to the new updates that have been made in SimLab Composer 9.1:

SimLab Composer:

Scene Building

- VR Package Importer and Exporter:
- Self extracted EXE exporter:
- Replace and align models:
- Tree transparency:
- Rename objects on double click:
- Apply Camera on double click:

HTML/WebGL Exporter

- Sun Environment
- HDR Environment
- Full Screen mode

VR Workbench


- Create Multiple 360s renders from the VR viewer.
- [Training Builder](#).

Renders

- Add two output render image sizes (2560x1440 and 3840x2160)


Automation

- [Visual Scripting](#).




SimLab Free VR Viewer:

Preview is not available



- VR Measurement mode (measuring distance VR environment)
- VR Web Browser
- [VR Catalogs](#)



- Video Action/Response
- VR Note
- New viewer menu: Loading and importing in the viewer, normal scene loading, importing model to an existing scene, new SimLab action for loading and importing
- New GUI for desktop and VR in the viewer
- Material Editor in the viewer
- Environment Editor in the viewer

SimLab Showroom:


- Number of packs for the showroom users 5 to 30 in each catalog (private and public)
- Images resizing and adding button in case the user have one model which will guide him directly
- New command line to handle downloading and starting package and executables

Composer GUI

SimLab Composer interface is based on selecting the workbench icon to work on. Upon selecting the workbench the allocated tools in that workbench will appear next. Primary tools, properties, task, and navigator panel in the interface will be changed to display the defaults of that selected workbench.

On the left hand side of SimLab Composer interface, from the workbench icon the user can select the workbench to use. Each one refers to a workbench in SimLab Composer. The workbenches will be active according to available license(s).


There are several elements that provide structure to how the commands are presented in the user-interface, as shown below. Shown in red are the Accessibility Toolbar, shown in green are the Specific Tools, and in blue is the workbenches Icon. Also as shown below, the application interface has different sections.



Workbench Icon

From the workbench icon the user can select the workbench to use. The workbenches in this icon will be available based on the acquired license. The available workbenches are as listed below, and each application and its corresponding functionalities are described in separate sections.

Workbench icon consists of two parts; the icon and a drop-down menu.



Materials

- Libraries
- Animation
- Scene States
- Sequences

NewMTL

- Ceramic
 - General
 - NewPattern
 - Pattern
- Crystal
 - General
- Fabric
 - Carpet
 - General
 - Pattern
 - Satin
 - Velvet

The material library displays a grid of 20 material preview thumbnails. The thumbnails are arranged in two rows of ten. The top row shows various fabric and carpet patterns in shades of blue, green, and brown. The bottom row shows similar patterns in shades of green, blue, and brown. The 'Carpet' material is currently selected and highlighted in blue.


Specific Tools

Once you select a workbench, the specific tools allocated in that workbench will appear next to the scene building primary tools.

The concept of additive tools helps orienting the user towards the appropriate tools without the cost of losing access the primary tools. SimLab Composer tools are arranged into menus depending on their nature of use.




As an example, clicking on the “move” icon, will display a menu of tools associated with the movement of an element, you can translate, rotate or scale an object among other operations via that menu.



Object Tree

On the left side of SimLab Composer, you can find the objects tree, the tree displays and arrange all the elements in your scene, including, geometries, lights and cameras to name a few.



- 1 Collapse Tree
- 2 Expand all objects from parents
- 3 Collapse all objects from parents
- 4 Switch font color black/white

5 Search for Objects by name


6 Align Object

7 Resize the object tree

8 Parent

9 Object

You can adjust the size and the location of the tree easily, as well as choosing whither to hide it or not.




Selecting an object will display the attributes box that contains all the properties for the selected object, through this panel you can perform several basic operations on the object, among which, are: translate, rotate, isolate and copy, In Composer 9, user can search for objects by name.



Sometimes this Object Tree displays application specific functions, like Render Settings, when the Rendering workbench is selected.


Accessibility Toolbar

Regardless of the selected workbench, this toolbar will be displayed at the bottom of the 3D area. This toolbar contains several functions that controls the behavior and appearance of the 3D area, as well as several tools for navigation and selection. It provides the user with different functions to set the view of the 3D are, as described below starting from left to right.



Select Object (Pick Mode)

When starting SimLab Composer the default picking mode is enabled. Picking returns two values; a location and a normal direction. The user can change the picking mode to the following:




The picking modes in SimLab Composer are:

1. Default Pick: in this mode the user picks a point in the model. The location and the normal direction at that point are returned. The geometry at the picked location will be selected in the Object Tree, and its bounding box will be displayed in the 3D area.

2. Pick Edge End Point: this picking mode will highlight the edge closest to the selected point, and the returned normal will be tangent of the curve at the closest end.
3. Pick Edge Loop: this picking mode is useful for selecting the center of a loop.
4. Pick Center Of Curvature: with this picking mode picking a curve will highlight the curve, and will display its center normal .

Window Configuration




This button allows the user to select the number of views, in the 3D area. The user can select to have:



Views can also be displayed by pulling the right and bottom edges of the 3D area.

View Mode

The default view mode in SimLab Composer is the Solid View. It displays models in solid view with edges hidden. The user can select one of the following view modes in SimLab Composer.

Button	Effect	Shortcut
	X Ray View	Alt + 1
	Edge Only View	Alt + 2
	Solid Illustration View	Alt + 3



Solid View

Alt + 4



Real Time

F4

1. XRay View; gives a x-ray effect to the models in the scene.
2. Edges Only View; displays only the edges of the models, in the scene.
3. Solid Illustration View; displays models in solid view, with their edges illustrated.
4. Solid View; displays models in shaded solid view.
5. Real Time; starts real time rendering for the 3D models in the scene

Default View Behavior

This function sets SimLab Composer to default behavior in, which is described in the following table.

Navigation	Mouse Button
Pan	Middle mouse button
Rotate	Left mouse button
Zoom	Right mouse button

Rubber band

This function can change the selection mode in the 3D area and it has three options:

- # Rubber Band Selection: Changes the selection icon to a square band, and allows the user to window select more than one geometry in the 3D area.
- # Append To Current Selection: The selection icon will show a '+' sign inside the square band. The user can window select more geometry in a different section of the 3D scene, without losing the previous selection.
- # Remove from Current Selection: With a '-' sign added to the band, the user can remove geometry from selection, without losing previous selections.

Camera Pan

This function changes the behavior of the left mouse button, to Pan.

Camera Zoom

This function changes the behavior of the left mouse button, to Zoom.

Fit all

This function automatically updates camera to fit all geometry in the scene within the active view area.

Zoom to Object

This function updates the camera in the active viewport, to zoom to the selected object. In case the user presses the button without selecting an object, a message will be displayed on top of the Common Toolbar asking him to do so.

Switch Between Parallel and Perspective View

This function switches the camera between perspective and parallel modes, in the active viewport. For engineers who are used to parallel mode, this option would be helpful.

Capture View image

This function allow user to capture image from the scene.

Navigator Panel

Towards the bottom of the interface, you can find Simlab Composer's navigator panel, this panel grants the user access to all the predefined elements available in Simlab Composer. Elements such as materials, HDR images, 3d models can be found in the libraries. An extensive set of predefined materials can also be accessed through the navigator panel.

In addition to the elements, SimLab Composer provides through this panel an access to the user created elements, some of which are scene states, walkthroughs and animations.



Materials Library

In addition to the elements SimLab Composer provides, this panel offers access to the user created elements, some of which are scene states, walkthroughs and animations.



Material Panel

In this panel, the user will have five buttons, as shown in the material panel image below.



Add New Material


Clicking this button will add a new item to the corresponding library.

Delete Material

This button will delete the selected item from the library

Manage Material

Clicking this button will display the Manage Library dialog, where the user can add new library(s), rename or delete existing ones.



The Manage Material Libraries dialog has more options. SimLab Composer, by default, comes with Composer materials library that has different groups/materials types. In this dialog the user can export, import, or merge different material libraries. Material libraries will be exported in (*.mlb) file format, and the packed libraries to import should have the same file extension.

Share Contents

With this feature, sharing different resources is simplified significantly. The rule is clear: if a resource exists in a library, then it can be shared.

Resources can be:

- Materials
- HDRs
- Models
- Background Images

- And even more...

To share a resource, just drag and drop it from a library panel to the area with the title Drop to Share and surrounded by orange dotted border, which is located on the panel of Sharing Resources tab. This procedure is shown in the following image:

Sharing Resources tab includes the following control elements, as shown in the following image:

- **Drop to Share:** It is an area where the user should drop in a resource.
- **Save Package:** It is a button that let you to export and save a package to be shared with colleagues or sent to SimLab team.
- **Load Package:** It is a button that let you to import a package into SimLab Composer.



The Sharing Resources tab displays a green tick (as shown in the following image) once an item is dropped into Drop to Share Area, indicating the operation is successfully finished.





You can include items of different types in same package.

Change View


The user can select the size of the items in the library (Large, Medium, or Small), as shown in the following image:



Changes to SimLab Composer's GUI are saved when the user closes composer.


Libraries

In this panel grants the user access to all the predefined elements available in simlab composer, elements, such as materials, HDR images, 3D models can be found in the libraries.




3D Models Library



The library panel, on the other hand, will change to show the Basic Shapes, Composer Scenes. This library provides users with quick access to frequently used 3D models. In this panel the user can add new items to the Basic Shapes group, and can delete others. Clicking the Manage Library button, enables the user to create new groups and manage existing ones, also can change the library view.




Download Contents




The user can separately download each downloadable content one at a time by double-clicking a downloadable content from the desired library, if the Download Content dialog box appears as shown in the following image.



The user can also download all contents related to the active library at once only in a single step by pressing the Download All Contents button (as shown in the following image) that appears on the Library toolbar. The Library toolbar is a vertical toolbar located at the left side of a Library as shown in the following image. The Download All Item dialog box (as shown in the following image) appears once the Download All Items button is selected.





After the download process is successfully completed, the new item(s) will be directly available in the corresponding library without the need to restart the Composer application.




Downloadable contents are available online, therefore an Internet connection is required in order to benefit from this feature.

Rendering Library

Background Image

This background setting option requires the user to browse to an image file to be used for the background of the rendered image.




Background Spherical

Spherical Background; enables the user to select (*.hdr), (*.exr), or any image file, that will be wrapped around a sphere or hemisphere, and select color, size and brightness. This option is added to give users more control since the Environment-HDR (global HDR) in the Render Settings dialog can be rotated, but cannot be scaled.


The user can click the Image in the Render Settings dialog, and browse to an HDR image file.

Then by clicking the '+' Add to HDR library button, the current image will be added to the library. A unique name should be given to each HDR image.



Presets

In the image shown below different settings were changed in the Render, Environment, and Background task bars that resulted in the rendered image shown. Clicking the add button in the render settings library, displays the Add New Item dialog. The name and preview image for the rendering can be entered, in this dialog. This will add the preview image to the library.



Sun

This environment setting simulates physical sky at different sun angles (Solar Elevation), which determines the time of the day. The sliders of the parameters of this environment option, makes it easy for the user to view the effect of each parameter, in real time.

The user can select to Enable Sun, in the render settings, in addition to enabling the HDR. The result will give the rendered image the sun shadow effect.

IES Lights Library

3-D interior and home design just reached a whole new level thanks to this new light category. Now, SimLab Composer supports IES data, an important factor for architecture visualization. Using IES light in your interior scenes can appear and produce more photo-realistic, as actual lighting effects are more realistically emulated. The IES Light Library in SimLab Composer (as shown in the following image) contains a collection of 29 pre-installed IES lights and all of them can help you generate a nice ambience lit interior environment for your renders.



The panel of the IES Light Library is located vertically at its left-side, presenting the following six buttons:

- # Add New Item: The Add New Item button allows the user to add new IES Light selected from the scene to any activated light tab within the IES Light Library. When this button is clicked, the Add New Item dialog box appears.
- # Delete Item: This command discards the selected light thumbnail from the panel of the activated tab.
- # Manage Library: The Manage Library button launches the Manage Library dialog box to give the user options to create, delete and rename light groups which are presented by tabs in the IES Light Library.
- # Download Contents: This task is the same as in the 3D Models Panel described in Navigator Panel.
- # Share Contents: This task is the same as in the Material Panel described in Navigator Panel.
- # Manage Material :This task is the same as in the Material Panel described in Navigator Panel.



Lighting is perhaps the most important aspect of CG. It really makes or breaks a scene. Once your lighting is ready, you will be able to render the scene.


Animation Library

Time Line provides the user with a tool to visualize and edit animation key frames. The time line is displayed by default in the Library panel of the Animation workbench.

In the timeline the user can also set the animation duration, by setting the end key frame value.

The current frame is marked on the time line by a red vertical line. The names of the animated objects appear on the left part of the time line, clicking on the name of any object automatically selects it in the 3D area.


The user can play animation by clicking the Play Animation button in the animation time line, or by hitting the Space Bar. The tool bar also includes the tool buttons Go to First Frame (Shortcut Home) and Go to Last Frame (Shortcut End).



It also includes the Director Record button, which can be used for managing animations from multiple cameras


Clicking on an animation key frame on the time line will show its properties, in the Properties panel. The user can change these properties, for different types of animation.

The user can also change the location of any key frame on the time line, by selecting then dragging it from a location to another.




The user can drag a selection box to copy multiple key frames. The user can delete all the key frames by clicking the Delete All Animations tool button in the time line.

In this Panel the user can copy ,move, delete or delete all the key frames in the animation timeline, by clicking the corresponding button. The user can also scale the time line.



Scene State Library

Scene States enable users to capture different configurations for the selected 3D model(s), or for the whole scene.



The User can check the properties to include in a scene state, from the Default Apply group in the task bar.


SimLab Composer's Scene States are smart in capturing attributes; they can include any combination of the listed attributes.

This can be helpful in creating scene states for models with different attributes, and setups. If the user needs to show different products with different materials or versions, SimLab smart scene states are the answer.

Sequence

VR Animation Sequences: Utilize animation sequences in your scenes and projects.

In the timeline the user can create interactive sequences that can be implemented in the VR experience in the Simlab Viewer




- Create an Animation Sequence: by clicking on this icon the user can create new sequence to use in your scenes.
- Show Animation Sequence List: This function button displays the list of sequences you created.



Utilize and employ Animation Sequences in your exported 3D PDF files or WebGL/HTML files; either by assigning them to any 3D object via SimLab Composer or to 2D elements of your templates via SimLab Template Designer.




VR Animation Sequences video tutorials:



Properties Panel

When geometry is selected in the 3D area in any workbench, this panel will display four tabs describing the selected geometry. The user can change the properties in this panel as following:



Object Tab:

In this tab the user can change the selected object name property. Other object properties that can be set in this tab include:


Hide/Show: by clicking this icon the user can hide/show the selected object in the 3D area. These two functions are available in the Object tab of the Scene Building workbench.

Freeze/UnFreeze: freezing the selected object will lock its position/orientation in the 3D area. All transformation functions will NOT be applicable to it, until this icon is clicked again to unfreeze it. These two functions are available in the Object tab of the Scene Building workbench.

Apply Actions: in this combo box, the user can select any of SimLab actions to apply to the selected object. Applied actions can be exported to 3D PDF files, as well as HTML (Web GL).

SimLab Actions:

SimLab Composer supports a number of predefined actions that can be executed upon clicking a 3D model, or clicking Templates' elements. Advanced users can write their own script to define new actions. SimLab actions can be executed in 3D PDF, and HTML files.



Action

Effect

URL	Links 3D geometry OR Template element with the entered web address, that will be opened On Click.
Animation Play	Stops playing scene's animation upon clicking 3D geometry OR Template element.


Animation Stop	Stops playing scene's animation upon clicking 3D geometry OR Template element.
Scene State	Executes a scene state upon clicking 3D geometry OR Template element. Scene states can be selected by Name or Index.
Message Box	Displays a message box upon clicking 3D geometry OR Template element. The user needs to enter the Message and its Title.
Script	Enables users to write their own script to be executed upon clicking 3D geometry OR Template element.
Pre-Populate	
Video Action	allow to play, pause, seek, toggle and play duration for the video which created from Make Video function from Visual Effects menu in the VR Worksbunch
Load Scene	Run another Composer Scene from the computer or online "URL link for the scene" in the VR Viewer.
Import Model	Import the model into the scene during experience the VR Viewer.

Multi Actions Option:

If the Multi Actions option is selected, clicking the Actions List button will open the Multi Actions List dialog. By clicking the '+' button the user can enter a list of actions of different types. The order of these actions can also be changed using the up and down arrows. These actions will be executed upon clicking the selected 3D geometry, and they can also be applied in 3D PDF templates.

Supported ways of applying the actions list are:

- # Loop; runs the action's list upon click in order, then from start again. That is action_1, 2,3 ..., then 1, 2, 3.
- # Swing; runs the action's list upon click in order, then backwards again. That is action_1, 2,3 ... then 3, 2, 1.
- # Random; runs the action's list upon click randomly.
- # Run All; runs the action's list upon click in order one time.



Scene State:

Executes a scene state upon clicking 3D geometry OR Template element. Scene states can be selected by Name or Index.

Play Sound:

Utilize and employ sound effects in your exported 3D PDF files; either by assigning them to any 3D object via SimLab Composer or to 2D elements of your templates via SimLab Template Designer.

Play Sequence:

Utilize and employ Animation Sequences in your exported 3D PDF files; either by assigning them to any 3D object via SimLab Composer or to 2D elements of your templates via SimLab Template Designer.

Transform Tab:

In this tab the location of the selected object and its pivot can be known, as well as changed with precise values. Also Scaling uniform/non-uniform can be done for the object around its center.


Both the Object and its pivot have Global, and Local locations/orientations. The Global location is the location of the object's center relative to the world's coordinate system. The Local location changes according to the transforms performed on the object, relative to its parent.

Attributes Tab:

In this tab the user can define attributes attached to the selected geometry in the 3D scene. These attributes can be exported to 3D PDF files, and when the 'Export Object Attributes' option in the Advanced tab of PDF Settings dialog is checked; This can help designers communicate BIM and metadata.

Material Tab:

In this tab the user can change the Name and Type of the material for the selected geometry. SimLab Composer supports different material types. Common properties between different types of materials are grouped in a common place in the Properties panel.



Different types of maps can be also applied to the material of the selected geometry, in this tab. These maps can have different effects on the look of the 3D model, thus reducing the needed modeling time and complexity. Each map has its own parameters that can be accessed by clicking the downwards arrow under the map's image file. The user can add a map to a material by clicking the '+' image, a material can also be deleted by clicking the 'x' button under the material image.

Texture Maps can be applied to any material type. The user can select to apply a texture file, and then fine tune the different parameters to get the required effect.

Bump Maps are used to simulate the look of geometric details on objects, so it helps the user avoid the inefficiencies when modeling these details in the geometry itself. Bump maps can be set to a texture of any format. Notice that even when a colored image is supported, it is still utilized as if it is in gray scale since bump map utilizes the intensity and not the color of the pixels.

The bump map basically simulates the effect of changing the surface level of the object, where bright pixels in the bump map image simulate heightened areas, and dark pixels represent lowered areas.

On top of the regular texture, scale, and offset properties, the bump map has one additional parameter, Strength which can be set to any positive value, and gives the user the ability to modify the bump effect where higher values make the effect stronger and more pronounced and therefore cause object to appear less smooth.

Normal Maps are similar to bump map, used to simulate the look of geometric details on a 3d object. The difference is that in the case of bump map, a gray scale image maps the height of the surface, whereas in the normal map a colored (RGB) image is used to map the direction of the normal in addition to its height. As such, a normal map enables finer control, but requires three channels (R,G, and B) to perform normal calculations.

Normal maps are generally generated by specialized software, which should give an RGB normal map image according to the desired effect by the user, in addition, lots of usable normal maps can be found on the net.

Opacity Maps give the user the ability to specify holes, transparent areas, and opaque areas on the mapped object. The image itself contains the opacity data in the following way:

- # Black pixels in the image map represent holes
- # Gray pixels represent semi-transparent areas (as brightness increases, opacity increases)
- # White pixels represent opaque areas


Roughness map allows the user to set an image based distribution of roughness for metal and plastic materials instead of a single value applied to whole material.



Roughness map:



Alpha Channel Emitter: Alpha areas of textures will turn transparent if used on an emitter.




Emitter material now support textures with alpha channel.


Smart Toolbar

Smart toolbar is added to the GUI of SimLab Composer to make your work even smoother, faster and easier.

The Smart Toolbar is small, simple, and powerful. It gives the user quick access to the most frequently used commands. This toolbar is considered as shortcut launcher. It will enable the user to use functions without the need to switch to Scene Build workbench.



The Smart Toolbar is found compound in the Object tab of the right panel, as shown in the image bellow.




It consists of the following buttons:

- **Select Objects Using Material:** allows you to select object(s) that have same materials.
- **Apply Materials To Selected Object:** allows you to apply materials to selected object.
- **Regenerate Material Icon:** a button, if clicked, will regenerate new icon/thumbnail images for the content of the corresponding library, for display purpose only.

Drag-and-Drop


In SimLab Composer, it is easy to copy a material from one object to another.

Click on the object to show its material in the properties panel, now you can drag the material icon and drop it on the new object to copy material properties to the new object, as shown in the following image.



Current Action Area

This area will display the last captured Scene State, in case of Scene States creation. In case of using any of the draggers in the Move task, a spin box will be displayed in this area. The user can input values in this box, or use its spin arrows, as shown in the following image.



Camera Snapshot

Capture Camera Snapshot

The Camera Snapshot Button is located at the leftmost on the 3D area, as shown in image below


Snapshot: This button allows you to capture formal camera snapshot quickly. A snapshot is generally the capture of an object's state at a specific moment in time.



Don't be confused between Snapshot button and Capture Image button. Snapshot is about preserving informative scene state to be used later, whereas Capture Image is about generating an image from the viewer as it is in the 3D-Area or a rendered image if rendering process is turned on.




To delete a snapshot or a collection of taken snapshots, go to the Scene State Library which you can find under the Scene State tab on the Scene Building ribbon after switching to the Scene Building workbench.




Messages Area

Some functions in SimLab Composer require the user to make some kind of action/selection. In this area of the application interface, messages can be displayed to inform the user about the required action, as shown in the following image.



View Cube

Use the View Cube to orbit your design or view the design from standard view positions. Click on the faces and corners of the cube to access standard orthographic and isometric views.



Composer Workbenches

SimLab Composer's unique trait is an extendible framework architecture that allows multiple workbenches designed for different purposes to collaborate and aid the user in achieving his objectives.

The workbenches system isolate particular main functions into separate categories to assist the user in quickly accomplishing his goals, and to eliminate the confusion caused by having a complicated interface that might hinder the user's ability to access the available tools with ease.

You can easily switch between workbenches, click on the workbenches icon at the top left corner and select the workbench suitable for your task. You can choose the scene building workbench, which holds the basic and primary tools found in SimLab Composer. You can also select the texture baking workbench. The animation workbench. The simulation workbench. The automation workbench. And finally the virtual reality workbench.

You can choose the scene building workbench, which holds the basic and primary tools found in SimLab Composer.

You can also select the texture baking workbench.

the animation workbench, or the simulation and automation workbenches.

Scene Building Workbench

SimLab Composer consists of a set of workbenches, Scene Building is the default workbench, when you change the workbench, the user interface and workspace will change accordingly.

Scene Building workbench is equipped with all the tools needed to build 3D scenes. Upon selecting this workbench, the workbench task bar will show the following tasks as shown in the picture below, File Menu, Move Menu, Create Menu, Geometry Menu, Material Menu, UV Menu, Scene States Menu, Render Menu, Image Effect Menu, Navigator Panel:






The refined scene building workbench video:



File Menu


In this part of SimLab Composer interface, the user has access to several applications such as, new, open, import, export, settings, register, help and more.



Scene Group

New/Open

Upon starting SimLab Composer, or clicking on the new button, the new scene dialog will appear. In this dialog the user can select to create a 2D ground scene, to open a scene, or to create an empty one. Images of the recent opened scenes are displayed in this dialog for a quick access. The last files list is also accessible from the arrow beside the open scene icon.




SimLab Composer is enclosed with short and brief learning videos.


The Getting Started Movies are essential to let you get started quickly and easily without the need for streaming services over a wired or wireless network connection to the Internet. They cover the following topics:

1. Introduction to Composer, its GUI, and its workbenches.
2. A tour within the Scene Building Workbench.
3. A quick tour on how to use Texture Baking Workbench.
4. A look at the Animation workbench.
5. An overview to Simulation Workbench.
6. A look at the Automation workbench.
7. A look at the Virtual Reality workbench.

The user can access any of the provided videos by clicking on Tutorials button, which appears at the top right corner of the New Scene dialog box, as shown in the following image. Once you click over the Tutorials button, SimLab Composer will launch your default Internet browser and display a list of movies to be played inside HTML5 technology, with the latest versions of Mozilla Firefox, Google Chrome, Safari, and Opera support.



The following image shows the home page of the Getting Started Videos, which it can be opened in an Internet browser prompting the user either to choose the desired movie page from a list or start playing the movie right from the player control buttons.



The user can access the new scene dialog box every time by clicking the new button from the scene menu located under the File tool.




We highly recommend you to always upgrade your Internet browser to have the latest version installed, in order to play and view the movies without problems.

Save/Save As

Both function buttons will open the Save Composer file dialog, where the user can select the name and location for the created *.sim file.

Pack

This function button displays "Pack The Scene" dialog, in which the user can create *.zip file based on the selected file format from the list.




The packed *.zip file will include all 3D models in the scene, along with their materials and textures. HDR files and BackPlates can also be included, if the user checks this option. Packing a scene is necessary for the user to share 3D scenes created in SimLab Composer with others.

Sharing Group

Sharing Group

SimLab Composer can be used as a sharing application. Users can share their 3D models and scenes with others in different methods that preserve models security.





Import/Export Menu

Import/Export

Both function buttons will open the corresponding Import/Export Geometry dialog. The import function enables the user to build scenes filled with 3D models from different file formats. The export function, on the other hand, enables the user to share the created 3D scene with others in different formats.


Clicking Import will display the Import Geometry dialog, where the user can browse the 3D geometry to import. Upon selecting a 3D file, the Import File dialog will appear as shown below. In this dialog the user can set different options for 3D import, including; Up vector; Z axis is selected by default. The user can choose a different access depending on the design of the imported 3D geometry. Scale and center; this option when checked will scale the imported geometry to fit into the 3D scene. It will also import it to the center of the scene.






Keep dynamic link: This option in SimLab Composer import function improves working with 3D design applications. It enables users to keep dynamic link/automatic update between the 3D model design application and SimLab Composer, when the 'Keep dynamic link' option is checked in the import dialog.

In the images shown below the house designed in Google SketchUp was imported into SimLab Composer, with the dynamic link checked. Different materials and texture were applied to the house model, in SimLab Composer and real time rendering was started.



In SketchUp the model has been changed/saved, where the garage area was made bigger. To keep the dynamic link, SimLab Composer issues a message informing the user about the model's design change.



In this dialog the user can save the model in SimLab Composer with the old design. Then clicking Update, with the Retain scene materials option checked, will update the design model while keeping SimLab Composer materials and textures.

Supported import formats

SimLab Composer supports importing the following industry standards CAD/3D file formats.

xaml	Standard format	√
3dxml	CATIA	√
skp	SketchUp (up to ver 2018)	√
3dm	Rhino (up to ver 6)	√

sldprt, sldasm	SolidWorks (up to ver 2016)	√ (Windows only)
sat	ACIS	√ (Windows only)
STEP	Standard CAD format	√
IGES	Standard CAD format	√
U3D	Standard format	√
3D PDF	Adobe Acrobat (U3D Based)	√
DAE	Collada (Standard format)	√
FBX	(up to ver 2016)	√
3DS	3DS	√
OBJ	Wavefront	√
STL	Stereolithography	√
DWG	AutoCAD (Up to 2018)	√
DWF/DWFX	Autodesk Standard	√ (Windows only)
DXF	AutoCAD	√
OSG	Open Scene Graph	√
ipt, iam	Autodesk Inventor (up to 2015)	√
X_T, X_P	Parasolid	√ (Windows only)
IFC	IFC	√
par, asm, psm	Solid Edge (up to ST6)	√ (Windows only)
Zim	SimLab Archive	√
Sim	SimLab Composer	√
PRC	Product Representation Compact	
JT		√
PRC	Product Representation Compact	
CTM	Compressed Triangle Mesh	
GoZ	ZBrush	√
Gltf/glb		√
Json		√

vrpackage	SimLab VR Viewer, VR Application	
-----------	----------------------------------	--

Supported export formats

3D Scenes built using SimLab Composer can be exported in the following file formats.


Export File Formats
3D PDF (*.pdf)
HTML 5 (*.html) +WEB GL
osg (*.osg)
osgb (*.osgb)
ive (*.ive)
obj (*.obj)
DWF (*.dwf, *.dwt)
DWG (*.dwg)
DXF (*.dxf)
SketchUp (*.skp)
3DS(*.3ds)
U3D (*.u3d)
KeyShot (*.bip)
Collada (*.dae)
FBX (*.fbx)
DirectX (*.x)
Indigo (*.igs)
STL (*.stl)
CTM (*.ctm)
Composer RT (*.xml)
JT Multi File (*.jt)
JT Single File (*.jt)
.prc

Simulation (*.json)
SimLab iPad File (*.zim)
SimLab VR Showroom (.vrzim)
SimLab VR Viewer (.vrsim)
.360sim
.360zim
.vrpackage

3D PDF

3D PDF

3D Scenes created in SimLab Composer can be exported into custom designed 3D PDF files, using SimLab Designer. The exported 3D PDF files can be opened using the free Acrobat reader (version 9.0 or newer), to take advantage of all the features in the generated 3D PDF file.



Features exported to 3D PDF files, as well as to HTML/WebGL files are listed in the table below.

Exported Features	3D PDF Files	HTML5/WebGL Files
3D models and Geometry	√	√
Textures	√	√
Materials and Colors	√	√
Scene States	√	√

Visualized Scene Options (Lists)	√	√
Animations	√	√
SimLab Actions	√	√
2D Polylines and Annotations	√	
Cameras	√	√
Reflection Maps	√	√
Bump Maps	√	√
Custom Designed Templates	√	√



In the PDF button, and before attempting to export to 3D PDF, the user needs to choose the PDF Settings for the exported 3D PDF file.



In the tutorial video below show you how export your models to 3D PDF and visualize it with others using the free Acrobat Reader.

Simlab Composer

Mechanical 3D PDF



 SimlabSoft


Export Button

PDF Settings

PDF Settings dialog enables the user to control the look and behavior of the exported 3D PDF file(s). To open PDF Settings dialog, click Settings in the 3D PDF button menu. The dialog has five tabs, described below.

Template Tab


Is where the user can select a 3D PDF template, browse to the folder containing the template to use, create New templates, Edit, Delete, or Refresh template(s). Clicking the New button will open SimLab Template Designer.



SimLab Designer is a simple SimLab application that enables users to design and save their own templates, to be used when exporting their 3D models into 3D PDF or HTML5/Web GL or iPad/Android. For more details about SimLab Designer, select Designer Help from the Settings/Help bar in SimLab Composer.

Page Tab

In this tab the user can add background music to the exported 3D PDF file, and a Password for protection, and attachment file . The user can check the Repeat option, to keep playing the music as long as the PDF file is opened.



File Attachments: Attach any number of any file format with your 3D PDF files exported from SimLab Composer.




PDF Document Fill Mode: Browse and select any 2D PDF or 3D PDF file document and set it as the Fill Mode for your 3D PDF exported using SimLab Template Designer.

3D Tab

In this tab the user can set the properties of the 3D area in the 3D PDF template.





- Show 3D Toolbar: shows or hides the 3D Toolbar in Acrobat reader when opening the exported 3D PDF file.
- # Show World Axes: Shows or hides the world axes, in the lower left part of the exported 3D PDF file.
- # Open Model Tree: Opens the 3D model's tree in the exported 3D PDF file.
- # Disable Selection: Disables/enables selection of geometries in the exported 3D PDF file.
- # Navigation Mode: The user can set the default navigation mode for the exported 3D PDF file to be Rotate, Spin or Walk. The user of the 3D PDF file can choose to change this default mode from inside the exported 3D PDF file.

Default Render Mode: Using this option, the user can select the default render mode to be one of the following (Solid, Solid Wireframe, Transparent, Transparent Wireframe, Illustration, Shaded Illustration, Transparent Bounding Box, Solid Outline, or Bounding Box, Transparent Bounding Box Outline, Wireframe, Shaded Wireframe, Hidden Wireframe, Vertices, Shaded Vertices).

Default Light Type: light type can be one of the following: white, day, night, bright, CAD optimized, cube, or head lamp.

Light Power: increasing this value increases the brightness in the exported 3D PDF file.

Navigation System: in this group the user can set the navigation mode, in the exported 3D PDF file. The navigation mode can be either Default Navigation; which tends to focus on one object in the scene, or SimLab Smart Navigation which is suitable for large scenes.

Cameras/Scene States: in this group the user can check the Show SimLab Buttons Bar option, and choose an option for navigating different cameras/scene states in the exported 3D PDF file. SimLab Buttons Bar can be:

- Artistic Arrows: arrows will be used for navigating between different cameras/scene states.
- Numbered Buttons: numbered buttons will be displayed to represent each camera/scene states.
- Preview Images: preview images of the exported scene states will be displayed to represent each camera/scene states. (Available only in SimLab Composer)

Automatic Transition: this option enables automatic switching between, the different cameras in the scene. When automatic camera is enabled, the user can select the Pause Duration, which is the time in seconds for which the camera will stand still before camera effect starts.

Animate Camera Transition is an option for animating the transition between different cameras in the scene. The Duration (seconds) is the time of the animated transition. In case of no animated transition.
Time before switching cameras = Pause Duration + Duration (seconds)

The user can select the camera effect to be Zoom, Roll or the two combined. The camera effect will take place for the camera effect duration. In case the Automatic Camera option is not checked, the 3D PDF file will be exported with the scene cameras, but will not automatically switch between them.

The Preview Image group is available for the user to choose to include or not to include a preview image for the exported 3D PDF file. In case of selecting an image, it will be displayed when browsing for 3D PDF files, to help the user in selecting the required file. This image will also be displayed when the user first opens the 3D PDF file. The image can be a rendered view image of the model/scene.


Animation Tab

In this tab SimLab Composer users can set the properties of the animation(s) in the exported SimLab 3D scene.

- Frames per second (FPS): is the number of frames played per second for all animations created in the exported 3D SimLab scene. This controls the speed of playing all the animations in the scene, a value of 5 will result in a slower motion animation than a value of 15.


Playing Mode: is the mode to use when the animation(s) reaches an end. The Repeat option will keep on repeating the animation(s), from beginning to end, as long as the PDF file is open.

Swing option will keep on playing the animation(s), from beginning to end then from end to beginning, as long as the PDF file is open. The Play Once option will play the animation(s) only once.



Advanced Tab

Document Java Script and 3D Java Script: Can be used by advanced users to insert Java scripts to control both, the PDF document, and the included 3D model. Java scripts can be applied to designed templates, to make specific actions. Details about Java script support in 3D PDF files can be found at: <http://www.adobe.com/devnet/acrobat/javascript.html>.



- # Make Protected / Disable Measurement: This option is available for users to protect their exported 3D models, as it will prevent measurements of the model in the exported 3D PDF file.
- # Preserve Images Original Resolution: If the PDF template includes an image, this option when checked will preserve the image's original resolution, and will increase the file size.
- # Full Screen: Check box; if checked will make the 3D PDF file start in Full screen mode.
- # Export Measurement and Text Annotations: Checkbox; when checked will enable exporting measurements and text annotations in a 3D scene to 3D PDF.
- # Export Polylines: When checked, 2D polylines in the scene will be exported.

Export Object Attributes: Object attributes defined in the Properties dialog, for any object, can be exported into 3D PDF files by checking this option. This can help designers communicate data with files' recipients.

Open file after export check box: Will open the exported 3D PDF file.

3D PDF Export

After setting the different properties/settings for the 3D PDF file, clicking Export will open the Export Geometry window. The user can browse to the location to export the file to, and can input the file name.




After clicking the Save button, for 3D scenes with Scene States, the Manage Scene States dialog will appear. This dialog allows the user to check the scene states to include in the generated 3D PDF file, and the order of the scene states in the file, by using the up and down arrows.

For scenes with no Scene States, and which include multiple cameras the Cameras Manager dialog will appear. This dialog allows the user to order, rename, and select cameras to be included in the generated 3D PDF file.

Export with Android/iPad support

In SimLab Composer GUI, the Export Toolbar was expanded to have the Android/iPad button. This option extends the sharing capability of SimLab Composer by allowing the user to export a single 3-D PDF file which is supported and readable by multiple platforms using Acrobat Reader (PC and Mac) or SimLab CAD Viewer (Android and iOS devices).

The images bellow show the same model using different render modes:




Tools Buttons

3D PDF Merge


This option enables users to merge two or more PDF files together. This can be used to append a 3D model to a company's header, or a project description available in PDF format. PDF files can be generated using different programs, such as; Acrobat, WinWord, PowerPoint, or Open Office. Different 3D PDF files generated using SimLab products can also be merged together.

Upon selecting this option the Merge PDFs window will open. In the Merge PDF Window the user can click '+' to add the PDF files to merge. Clicking will remove the selected file from the list, and the up and down arrows changes the order the files to be merged in.



3D PDF Embed


3D PDF template files can be embedded into WebGL/HTML. Clicking this function button will open the Embed PDF inside Html dialog. In this dialog the user can choose the PDF file to embed, or create a new file. The Embed Fonts In HTML check box will include the template fonts in the exported PDF file. After setting all parameters, clicking Export will open the Export dialog. The user can input the file name, and choose its location, and then click Save.




WebGL

WebGL

HTML templates design is fully supported with advanced 2D layout. Behavior Actions can be exported into HTML5/Web GL, enabling users to create interactive 3D experience on the web. Reflection maps, sun light and shadow are applied to 3D models and exported to HTML, giving them more realistic look with smother camera navigation and better appearance for materials. 3D scenes can be exported into html5 files, the same way 3D PDF files are exported.



In the WebGL task bar in the Sharing workbench, click Settings to open Html5 Settings window. In settings window the user can select the template to use, and choose the other html export settings. With a template selected, click the Export button, then enter the name and location of the (*.html) file and click Save.



For 3D scenes with scene states defined the Manage Scene States dialog will appear upon clicking Save. There the user can check the scene states to include in the exported html file, and their order.



Export billboard objects, created in SimLab Composer, to 3D-PDF and WebGL (Web/HTML).



Export Toolbar

HTML5 Settings


HTML5 Settings dialog enables the user to control the generated HTML file(s). Before exporting to HTML, the user needs to select a template to use for export, and to set other HTML parameters.

Template Tab

Template tab is where the user can browse the folder containing the HTML template(s) to use, and create New templates, Edit, Delete, or Refresh template(s).

Clicking the New button will open SimLab Designer window. SimLab Designer is a simple application that enables users to design and save their own templates. For more details about SimLab Designer, select Designer Help from the Settings/Help bar in SimLab Composer.


Embed Fonts In HTML option, when checked, will include the font used in the template, in case of using distributable fonts.



3D Tab

In this tab the user can set the properties for the 3D Area. The 'Keep Camera Above Ground' option, allows architects to prevent viewers of their 3D models from viewing under the buildings, also user can enable/disable the Shadow from the sun, the reflection and the Sun Environment.

The user can also select the navigation mode in the exported HTML file. Spin navigation mode adds great navigation experience.




Navigation Mode: The user can set the default navigation mode for the exported 3D PDF file to be Rotate, Spin or Walk. The user of the 3D PDF file can choose to change this default mode from inside the exported 3D PDF file.

Animation Tab

In this tab SimLab Composer users can set the properties of the animation(s) in the exported SimLab 3D scene.

- Frames per Second (FPS): is the number of frames played per second for all animations created in the exported 3D SimLab scene. This controls the speed of playing all the animations in the scene, a value of 5 will result in a slower motion animation than a value of 15.
- Playing Mode: is the mode to use when the animation(s) reaches an end. The Repeat option will keep on repeating the animation(s), from beginning to end, as long as the PDF file is open.


Swing option will keep on playing the animation(s), from beginning to end then from end to beginning, as long as the PDF file is open. The Play Once option will play the animation(s) only once.



Advanced Tab

Document Javascript and 3D Javascript can be used by advanced users to insert Java scripts to control both, the HTML document, and the included 3D model.

JavaScripts can be applied to designed templates, to make specific actions. Details about Javascript support in WebGL can be found at the scripting help in SimLab Composer.




Message Box Tab

In the new WebGL exporter, user can make a message box in the HTML by select **Message Box** from **Action** into **Properties Panel** for any objects in the scene, write the message and the title of the message there.

Action	
Type	Message Box
Message	Welcome Message
Title	Hi there


In the message box tab, user can select the style of message box which display in HTML file.



There are four styles at the moment:

Style Name	Style
------------	-------

Style1




Style2



Style3



Style4



Android/iPad


Android/iPad

3D Scenes created in SimLab Composer can be exported into iPad/Android. The exported scenes will be saved in SimLab Archive File format (*.zim), readable by [SimLab CAD viewer](#). SimLab CAD Viewer can be installed from Apple iTunes and Google play. Information exported to iPad/Android includes: geometries, normals, materials, textures, cameras, animation, scene states, and SimLab templates.

Templates for iPad/Android viewers


Templates created for SimLab iPad/Android viewers should be created as follows:

From Android/iPad Settings dialog, click New to open SimLab template designer. The Page Size dialog will appear, create a page with an aspect ratio close to the aspect ratio of the device you are exporting to (aspect ratio is width to height percentage). For iPad the aspect ratio is 4:3, so a page with 1000 pixels width and 750 pixels height will be ok.




Add a 3D area that covers the whole template page. In the properties dialog on the left, the user can select the Background Fill Mode for the 3D area to be:

- Transparent
- Single Color
- Image



On top of the 3D area add images/text, and link them to messages, URLs, or scene states.

Add images for different products, and different materials along with links to their scene states created in SimLab Composer. Other actions can be added to an image, as described in SimLab Actions section.



You can download android and ios for our VR/AR app [here](#)

Export Toolbar


iPad /Android Settings

iPad /Android settings dialog consists of four tabs:

Template Tab

Template tab is where the user can browse the folder containing the HTML template(s) to use, and create New templates, Edit, Delete, or Refresh template(s).

Clicking the New button will open SimLab Designer window. SimLab Designer is a simple application that enables users to design and save their own templates. For more details about SimLab Designer, select Designer Help from the Settings/Help bar in SimLab Composer.



3D Tab

In this tab the user can set the properties of the 3D Area in the template.


The 'Keep Camera above Ground' option allows architects to prevent viewers of their 3D models from viewing under the buildings.

The user can also select the navigation mode in the exported (*.zim) file.




Tip The Spin navigation mode adds great navigation experience.

In the Light Power spin box, the user can increase/decrease the light power in the generated template and thus in the exported (*.zim) file.



Animation Tab

For scenes that include animation, checking the Show Time Line option will display the time line on top of the template.




Advanced Tab

In this tab, and by checking the Make Protected option, the exported (*.zim) file will only be viewable using SimLab CAD Viewer. The file will not be readable by SimLab Composer, and thus the 3D models included in the file are protected.

The Export Polylines option, when checked, enables exporting polylines included in the 3D scene.

Checking the option Include Dictionary will make the current values set in the dictionary to be saved in the generated zim file.




Cloud Group

Retrieve

This function button will open the Onshape's cloud. It's a way to import CAD data in SimLab Composer. Onshape is integrated with SimLab Composer, that means cloud-based documents can be imported to SimLab Composer right from Onshape's cloud storage.


Using SimLab Composer along side with Onshape is made easy, since most CAD file formats can ride in.

With Onshape, CAD data is kept available anytime and accessible from anywhere. Also the user can get the models directly on Onshape clouds.



The user can get your models directly on Onshape clouds!


As you see in the image below, from this window you can navigate the files on the cloud server, it is similar to the interface of the Onshape cloud system. You can access your documents, the files you created, your shared files, and also the public server. Once you select a folder from the list, the contents of this folder will be displayed in the documents list. Then select a document to display all the elements included in that document. After that select an element and Click import to access the selected design from the OnShape cloud server through SimLab Composer.



Publish

This function button will open the Sketchfab's cloud. Sketchfab allows you to store your models on a cloud server, and allows you to view them and share them online.

To create one, please Press on Sketchfab button and create an account.





The user can upload the models directly on Sketchfab clouds!

SimLab Composer will start preparing your scene to be uploaded, once the process is completed, a message will appear notifying you that the preparation is done, and that your model is being uploaded (as you see in the image below).

Export To Sketchfab

Model Title

Model Description

Tags

Change User OK Cancel

Once the uploading is completed you will get a message with a link to the uploaded model, the message will also ask you whether you need to copy this link to the clipboard in order to be able to use it by pasting in a web browser. (as you see in the image below).

Upload Successful

Upload Complete, You can find your model at: <https://sketchfab.com/models/60f9ba3565d847d991c5d306c441868e>
Copy it to your clipboard?

Yes No

Settings Group

SimLab Composer interface is based on selecting the workbench to work on first. From the file workbench icon you can find **Preferences**, and **Register**.

Preferences:


The user can change settings in each created scene separately. In other cases it would be easier to set the common settings to be used when creating new scenes. This can be done in the Preferences dialog. This dialog has five tabs, described below:

This can be done in the Preferences dialog. This dialog has five tabs, described below;

Directories Tab

In this tab the user can change the default directory(s) for Textures, Material libraries, Object libraries, and Templates used for exporting to 3D PDF, HTML/Web GL, and iPad/Android.


Advanced users may select to move the User Data directory to a new location; the user should copy the original data to the new location before setting the new User Data folder.



Camera Tab

Keep above Ground; if checked the camera rotation will stop at the ground level, and won't go below. This option is applicable to Parallel and Perspective cameras.

Background Color; is the color of the scene's background in SimLab Composer. To display the selected background color, check Preview Background in the Background Settings, under the Render menu, and uncheck the Preview Environment.




TIP

To set a Background Image for the 3D Area, that is invisible during rendering:
Go to Setting/Help bar » Preferences » On the Preferences dialog box » Camera tab » Background section » Select Image combo box » Browse to select an image.

Import/Export Tab

Automatically transform imported models; when checked, the first imported model will be automatically transformed/scaled by the value entered in the 'First model size to world size' text box, to the largest dimension of the world size of that scene. The model will be placed in the center of the world.

The same transform/scale will be applied to all imported models in that scene.



Polylines Geometry: in this group the user can select to import measurement and text annotations created in the design CAD package. Importing polylines can also be checked, and the width of the imported lines can be specified. In the image shown to the right, the same model was imported


twice, with import measurements and polylines options checked. The first time Line Width was set to 1.5, and then to 5.0 in the second. As can be seen in the image the trees branches are wider in the second time.

Export Units: are units to be used when exporting 3D models from SimLab Composer. By default SimLab Composer uses meter units, and the user has the option to select different units. All numbers will be converted to the selected unit to maintain the correct size of the exported object.

Automatically generate texture coordinates; texture coordinates for the imported geometry will be automatically generated when this option is checked.

Scale preview image of textures.

Appearance Tab



In this tab the user can set the preferred appearance options for SimLab Composer, including:

Language: this option allows the user to select the language to be used in SimLab Composer from the supported languages combo box. Changing the language takes effect after restarting SimLab Composer.

Tree Transparency: this option allows the user to change the transparency for the background color for the objects Tree.

Picking: this option allow the user easy to picking the arrows for rotate, scale and transform the objects, for example if the user set it equal 1 then need to select exact the arrow for the transform, but if the user set it equal 10 then can picking the transform arrow even when the user click near it.


Style Group: enables the user to select between two available styles, for SimLab Composer's interface. Changing the interface will take effect after restarting the application.

Fixed View Group: if the view mode in the Common toolbar is set to Fixed Size, the values for the Width/Height entered in this group will determine the size of the 3D area.

Preview Images group: these preview images are the ones used in the Basic tree. Thus if the Generate preview images option is unchecked, no images will be generated. A basic 3D Geom image will be displayed instead. If it is checked the user can set Max generation time, which is the max time in seconds spent in generating preview images for the selected geometry, all the way up to its top assembly. The caching for these generated images will be kept, thus if the maximum generation time was not enough to generate all images the first time the geometry was selected, they can be generated the next time.

Renderer Tab

This tab will appear only, if your computer support new renderer.



Register

Clicking this option will display the License Dialog, where the user can manage the Composer license. The user can buy professional licenses, or get free trials. For more information about requesting/activating a license go to : <http://www.simlab-soft.com/simlab-composer-license-step-by-step.aspx>

SimLab Composer 9.1



SimLab
SOFT

- **Buy**
- **Get Free Trial**
- **Activate**
- **Help (Step By Step instructions)**


Close

Help Group

Help

Under the Help menu the user has access to different help documents, including;

- Composer help document.
- SimLab RT Renderer help document.
- SimLab Designer help document.
- SimLab Scripting help document.




Tutorial

You can access the [online tutorial page](#) on our website for more tutorials.

Move Menu


In this menu all functions necessary for positioning geometry in a 3D scene can be found.



Transform Group

Transform


When the user clicks any dragger in this tool task, a small scroll combo box will appear, at the current action area, at the top right corner of the 3D area. The user can use this box to input exact numbers for translation/rotation/scale or can just scroll up and down. If the user prefers to freely drag the 3D geometry, this can be done using the dragger in the 3D area. Different draggers are described in the table below.



Snap Group

Snap

The snap functions are used for aligning 3D objects.



Snap to Ground: snaps the selected object(s) to the ground.

Snap To Object: snaps the selected object(s) to a target object.


Align: Align selected object(s) along a user defined axis, can be used in conjunction with SimLab composer picking modes.

Dynamic Snap: it's a smart tool that aids the user in placing objects in accordance with its surroundings. When activated, a blue box will envelope the selected object which in turn will snap and collide with nearby object giving the user a guide on how to place the object without penetrating other objects in the scene.

Pivot Group

Pivot


The pivot of a 3D geometry is the point which transformations applied to that geometry will be done.



- # **Show Pivot:** When toggled on, this function will display the selected geometry's pivot point and grant control over its location and rotation.
- # **Move Pivot:** This function allows the user to snap the pivot point to another point location. The user can make use of the Pick Mode options described in the Common Toolbar, to help in selecting the point's location accurately.
- # **Snap Pivot:** This function requires the user to select two points, and the pivot of the 3D geometry will be snapped to the center between them. the user can make use of the Pick Mode options described in the Common Toolbar, to help in selecting points accurately.
- # **Reset Pivot:** This function restores a modified pivot location to the center of the selected geometry.

Create Menu


This menu provides the user with the ability to create different scene elements that can add value to the 3D scenes.



Light Group

Light


This function has the supported light types in SimLab Composer, which are suitable for interior scenes. Users can add any of these light sources in addition to the light sources included in the environment image. Light sources in SimLab Composer - except for the Camera Head Light- are exported to 3D PDF and HTML.



Point Light

Selecting this light type will create a spherical Light Source geometry and add it to the scene. Point lights can be moved and positioned, using any of the move draggers. In the image below three point lights were added to the scene, and were snapped to the side lamps' geometries using the Snap To Object tool in the Object task bar. Fine positioning was also done using the Move 3D tool.

The light properties can be found in the Properties panel, to the right of the 3D area. There the user can edit a light's properties, like changing its color, or its power.




Area Light

Depending on the effect the user needs, this is another light type that can be used. As shown in the image below the same scene is now lit using an area light.

Same like Point lights, area lights have parameters that the user can change in the Properties panel.

Spot Light

Spot Light is another light type that can be created in SimLab Composer. In addition to the main light properties, spot lights have Cone Angle property that sets the angle of the light.



Directional Light

Directional lights are for exterior scenes. The user can change the direction of the light but not its location. Other parameters for this light include, light Color, light Power, and light Name.

IES Light

3D interior and home design just reached a whole new level thanks to this new light category. Now, SimLab Composer supports IES data, an important factor for architecture visualization. Using IES light in your interior scenes can appear and produce more photo-realistic scenes, as actual lighting effects are more realistically emulated. The IES Light Library in SimLab Composer (as shown in the following image) contains a collection of 29 pre-installed IES lights and all of them can help you generate a nice ambience lit interior environment for your renders.




If you have already purchased the corresponding license, you can find the IES light toolkit in the Scene Building workbench in the Light tab.



The IES Light toolkit includes the IES button, the IES Light Library, and the IES Light Properties Panes which appears at the right-side of the application window if an IES Light is selected in the scene.

The toolbar of the IES Light Library is located vertically at its left-side, presenting the following three buttons:



- # **Add New Item:** The Add New Item button allows the user to add new IES Light selected from the scene to any activated light tab within the IES Light Library. When this button is clicked, the Add New Item dialog box appears.
- # **Delete Item:** This command discards the selected light thumbnail from the panel of the activated tab.
- # **Manage Library:** The Manage Library button launches the Manage Library dialog box to give the user options to create, delete and rename light groups which are presented by tabs in the IES Light Library.



IES light files are created by many major lighting manufacturers and can be downloaded freely from their sites. One of such lighting manufacturer is Lithonia Lighting (www.lithonia.com) which has an extensive library of IES files in different categories.



Lighting is perhaps the most important aspect of CG. It really makes or breaks a scene. Once your lighting is ready, you render the scene.

Portal

Portal rendering is an optimization technique in SimLab Composer to avoid unnecessary calculations as possible. This is an advanced feature used to link two divided adjacent zones (indoor and outdoor) through opening objects. These openings are referred to as portals. Portals are best suited for indoor scenes, such as windows, doors, and tunnels.



For example, you are trying to simulate a sunny day, and beyond the direct light coming through the window, it's pretty dark. This feature will be a good tool to use in this situation by converting the window or part of it into portal, it gives you an efficient way of using a scene's existing sky lighting within interior scenes that do not require very long render times. A portal acts just like a mental ray area light. This light gets its brightness and color from the environment already in your scene.

New Portal

New Portal: This button is used to create a portal from scratch.

To Portal

This button is used to convert a selected object's face to portal.



To distinguish if an object is portal or not, a Portal Icon appears on the Object Tab of the Properties Panel on the right side of the application when the object is selected.



The New Portal tool only allows you to create portals in the form of square, whereas the To Portal tool allows you to create portals from any kind of shapes.


Shapes Group

Shapes


The Shape toolbar is provided to give you more control over creating particular basic shapes . This is applicable for Plane, Boxes, Spheres, and Cylinders.

The Shape toolbar (as shown in the following image) contains three buttons:


- **Plane:** a button that allows users to create a Plane by entering Center coordinates, Width, Depth, and Height of the box parameters in its dialog box which appears if clicked. The below Figure shows the Create Basic Shape dialog box for Plane.




- **Box:** a button that allows users to create a box by entering Center coordinates, Width, Depth, and Height of the box parameters in its dialog box which appears if clicked. The below Figure shows the Create Basic Shape dialog box for Box.




- **Sphere:** a button that allows users to create a sphere by entering Center coordinates and Radius of the sphere parameters in its dialog box which appears if clicked. As shown in the following image, the Create Basic Shape dialog box for Sphere.



- **Cylinder:** a button that allows users to create a Cylinder by entering Center coordinates, Radius, and Height of the cylinder parameters in its dialog box which appears if clicked. As shown in the following image, the Create Basic Shape dialog box for Cylinder.




Click OK to confirm object creation upon entered parameters.




Paths Group

Paths

Different paths can be created in the Path group. The user can create Open, Closed, or Circular paths. To activate a path, the user can select it from the Object Tree. Paths can be used to create Path Animation. Upon clicking any path function, a message will appear in the Message area, asking the user to start picking the path points. Approve and decline icons will appear at the top left corner of the 3D area to end selection.



The user can create paths as points in 3D or on plane.




The paths toolbar (as shown in the first image above) contains four buttons:


• **Composite**

To create composite path, follow the steps below:


1. Click [Create](#) → **Paths** → **Composite**, When you click on it, the **Path Creation** dialog will appear.
2. In this dialog there are two methods to pick points: **in 3D or On Plane**, select on plane then click **OK**.




3. In the message below, you can create paths by three ways: **Line Segment**, **B-Spline** or **ARC Line**, select **B-Spline**.




4. Now, **Start drawing** the path on the plane, click on any position in plane to put the start point, then put the second point etc.
When you finish, click **OK**.




5. To **edit the path**, select any point on path then **move** it.



- **Circular:** when clicked, the Composer ask you to select the position for center point of the circle. Then select the position of the point on circumference (Radius) for the circle.




- **Apply Tangents:** when clicked it will ask you to select a hard point that belongs to the 3D object. A tangent is a straight line that touches a curved surface at a point, but if extended does not cross it at that point.
- **Generate From 2D:** create a 2d path from the outside edges of the 3d objects.



Feature Group


Feature

In this function we are going to talk about SimLab Composer's features that would allow you to perform basic modifications and improvements to your 3D models in order to improve the realism of your design's appearance without needing to revert to a CAD application.



Sweep tool

After finishing draw the path creation process. Set the rotation for the sweep profile then click on the green mark to create the






To create Sweep, Follow the steps below:

1. Open the SimLab Composer
2. To create **Sweep**, you must create two **Paths** first, one's for sweeping along on it, and the second for a profile of the sweep.
3. Click **Create** → **Feature** → **Sweep**.
4. When you click **Sweep**, the message will appear in message dialog, select path which you want to sweeping along on it, then click **OK**.
5. Now select the second path to set it as profile of the sweep then click **OK**.
6. Finally rotate the profile path in demand then click **OK**.

Extrude tool

In the extrude window you can enter the height of the extrude.



Wire tool


In the wire creation window you can select the type of wire you are about to create based on the shape of its section.



You can choose from a circular shape, a rectangle, or a fillet rectangle.




Creating wires:




Street tool

Simlab Composer's street creation feature is a friendly tool that expands your designing capabilities and allows you to reach high potentials with your architectural Model effortlessly and efficiently.



To create 3D Street using SimLab Composer, Follow the steps below:

1. Open the SimLab Composer, you can start the program by double-clicking its **desktop shortcut** or from the **start menu**.
2. To create 3D Street, you must create [a Path](#) first.
3. **Select the path** which we have created, then click [Create](#) → **Feature** → **Street**, the Street Creation dialog will appear.




4. In this dialog you can find different **type for street: a Flat Shape, an Elevated, or an Elevated With Pavement.**


Flat




Elevated



Elevated With Pavement



5. Also you can set the **textures** for street and pavement once you **click on (+)** in the textures side in the window, when you finish, click **Create**.




6. Now the street creation will appear as a new object in [Objects Tree](#)

Annotations Group

Annotations

In this function we are going to talk about adding annotations and measurements to your design in Simlab Composer, and how you can manage the measurements to create a professional presentation that facilitates communicating and sharing your design.


In this dialogue we are going to determine the plane on which we are going to create the annotations. Selecting the proper plane for the annotations creation is crucial in terms of where the annotations will be projected for viewing.



TIP

You also have the option to offset the plane you have selected parallel to its axes.

Create Annotation



SimLab Composer allows you to create several types of annotations.


- **Linear dimension tool**, measures the projected distance between 2 points on the principal axes while the aligned dimension tool measures the distance between two points in space without projecting their location on a principal axes.
- **Radial dimension tool**, a button that allows users to create a box by entering Center coordinates, Width, Depth, and Height of the box parameters in its dialog box which appears if clicked.
- **Angular dimension tool**, can measure the angle between two intersecting lines.
- **Leader annotation tool**, allows you to add custom text with a pointer to the design.



Notice that the linear tool measured the projected width of the two points and not the distance between them.




You can change the measurement unit used from the annotation dialogue box, select a measurement unit that is suitable for your design



Bounding Box Group

Bounding Box

Bounding box is a tool that creates a ghost box for a single object or a group of objects, the ghost box can then be used in the boolean operations to modify the geometry of an object.




To create a Bounding Box, select an object or group of objects first, then click **Create** → **Bounding Box**, the Bounding Box will appear as new object in [Object Tree](#).

Camera Group

Camera

This menu includes all the necessary functions for creating, and setting the different cameras in a 3D scene also user can apply the camera by double click.



Billboard Group

Billboard

The Billboard lets you create geometry that is camera-aligned. The objects always align to view default or connected camera. The plane geometry linked to the Billboard will rotate around the local Z axis to face the viewer. The Billboard is centered on the object (plane) which is linked to it.


To create a Billboard:

1. Go To create tool »Click the Billboard button on it.
2. Enter settings as desired in the corresponding fields of the Create Billboard dialog box.
3. Click OK

After positioning a tree, for example, it will render as a well-behaved Billboard.

The Create Billboard dialog box (as shown in the following image) requires the following data:

- Position: Click anywhere in the 3D Area to pick a position (X Y Z) to place the billboard at.
- Image: Browse and select an image (choose PNG image format to preserve transparency). The default image will be a tree if the user didn't select an image.
- Height: Enter the suitable height that you wish in meters. Because it depends and takes the aspect ratio of the selected image, the width of the Billboard will be approximated automatically.
- OK: Confirm and accept billboard's settings.
- Cancel: To exit Billboard creation mode.







Not selecting an image results to tree image.



Billboards are always kept aligned with the camera.



New billboard object was introduced. The billboard object always faces the camera, to allow architects to add PNG trees and humans to the scene, as shown in the following render.



Decal Group

Decal

Applying a company Logo, or product images to 3D models is made easier with create Decal. Clicking this function will open the Decal window. The parameters in this window are;

- Image: requires setting a valid path for a valid image file.
- Rotation: is the rotation angle, in degrees, to be applied to the decal image.
- Scale: is a uniform scale value to be applied to the decal image.
- Depth Factor: is the depth value for applying another image of the decal, in case of applying the decal on more than one geometry.


After selecting an image, the user needs to pick four points, and a center to set the image location.

To learn more about decal creation, check SimLab Composer tutorials at: <https://www.youtube.com/watch?v=7U8Dh6H9K-Y>.

Decal

1

2



4

Center

3

Image

...

Rotation

0.0



Scale

1.000



Depth Factor

1.000




Generate

Close

3D Text Group

3D Text

Clicking this function will open Create Text3D dialog, where a user can type in text, and select its format. Clicking the OK button will create 3D text parallel to the ground in the 3D scene. An assembly with geometry for all letters in the text will be added to the Object Tree. Different transforms can be applied to the text. A user can also change the material of the generated 3D Text, by dragging material from the materials library, and dropping it on its geometry in the Object Tree.



To modify anything in the created 3D text, select the text in the 3D area, or in the Object Tree, to display its properties in the Properties Panel.

Object Transform Attributes

3DString "Simla..."

String Simlab Soft

Font Arial Black ,0.15

Depth 0.04

Left Justified

Section Plane Group

Section Plane


Newly created section plane will be selected in the 3D area with the 3D dragger to enable the user to transform/rotate the section plane.

Section plane effects are exported to the generated 3D PDF files, rendered images, and exported file formats such as OBJ.

By default a section plane cuts through the whole scene. Using the Break Using Section Plane tool, the user can select the geometry to cut using section plane(s).


In the image shown below a scene with three spheres inside each other and three section planes were created with different orientations. Select each section plane and use it to cut through the outside and the middle spheres. To do that go to Geometry task and with the sphere to cut being selected, click the Break by Plane function button. This will break the geometry into two in the object tree and the 3D area.

Repeating this for all three section planes will split each sphere into eight parts. Deleting / hiding some of the parts will result in the shown image.



Geometry Menu

This menu provides the user with geometry related tools.



Break Group

Break Geometry

The smallest representation of geometry in SimLab Composer is 3D Geometry. 3D Geom is a geometry that has one transform and one material applied to it. All contents of 3D Geom are moved together, and must have the same material.

Some model formats do not support saving Object Tree structure, when importing 3D models of those formats, 3D Geom can contain many none connected parts. The Break geometry tool enables the user to break a 3D Geom that contains none connected parts into multiple 3D Geoms. Each one of the new 3D Geoms can be moved separately and can be assigned a unique material.

Break Faces

This tool will break the selected 3D model into its faces. Each face will be converted to 3D Geom, and added to the Object Tree. Unique materials can be assigned to each face. In the above stool example, the top geometry with a different material was broken into its faces as shown in the image below. Different materials were applied to the different generated faces.

Break by Plane

This tool enables the user to select the geometry to cut through using a section plane already created in the scene, using Create Section Plane from the Create task bar. Using the same section plane with different orientations, different cuts can be done on the geometry.


Break Instances

Instances in SimLab Composer are multiple duplicates of an object using the same materials' structure, and same transforms as the original object. Using this function the instances can be broken, thus each one can have its own materials/transforms.

Explode Group

Explode/unexploded

Explode function makes it easy to show the components of an assembly. When selected the explode geometry dragger will appear, allowing the user to explode the selected object(s) in the X, Y, and Z directions. The user can also rotate the dragger to select an arbitrary vector to be used for exploding the assembly.



Exploding Geometry:



The user should click either the Approve or the Decline mark in In the central part of 3d area, when done with exploding the geometry. Clicking the red

Decline mark will cancel the operation of creating the exploded view. After completing the explode operation the user can go back to the original model by clicking UnExplode.

Tools Group

Merge on Material

With an assembly selected in a 3D scene, selecting this tool will merge geometry using the same material into a single geometry. In the image shown to the left, the three selected geometry in the car model are using the same material. In the right image the Merge.

Smooth Normals

this tool can be used to average the normals of the geometry to appear smoother during rendering

Flip Normals

Clicking this tool will have the selected objects normals flipped.

Combine Vertices

Vertices having the position and normal direction will be replaced by a single vertex, using this tool. This will reduce the size and complexity of a 3D model.

Info

Clicking this tool will display Geometrical Info dialog, showing the number of Objects, Vertices, and Polygons in the selected geometry. Knowing the number of vertices and polygons can help a user estimate the size of the output file. This might make the user ignore some details, for sharing efficiency.


Voxel Group

Voxelize Task

Voxelizing a 3D model is rebuilding the 3D model using building blocks (voxels), like LEGO. The user can choose the building block to use for voxelization, and can choose to voxelize the whole scene, or the selected geometry. Notice that this will add a significant number of polygons to your 3D scene.

The Voxelize Options dialog will appear, when clicking any of the voxelization options. The default voxel object is a cube of certain size, and the user can choose a different object, by clicking the Pick voxel option. The voxel object needs to be a geometry in the scene, and the user can just pick it.

The Combine voxels based on material option, if checked, will combine all voxels, based on material, each in one geometry in the Object Tree. If not checked each voxel will have its own geometry in the Object Tree.





To convert any 3d model to Voxelize model, Follow the steps below:

1. First, export your model from any 3d software as one of the [Supported Import Formats](#) in Composer.
2. Open the Composer, you can start the program by double-clicking its shortcut or from the start menu.
3. To [Import](#) your model in Composer, click **File → Import**, or by using **Ctrl+I**, then select your model format and click **Open**.
4. When you click Open, the Import File dialog will appear, In this dialog you can set different options for 3D import, select **Z axis** in up vector, **Scale and Center**, then click **OK**.
5. Now your model imported in Composer.
6. Select your model in Composer and click on **Geometry → Voxelize** Selection, the Voxelize Options dialog will appear, the default voxel object is a cube of certain size, and you can choose a different object by clicking the pick voxel option then select another object Ex: Sphere, Cylinder or any object in the scene, then click **Start**.
7. When the convert operation complete, the result will appear as a new object in [Objects Tree](#).




The less the value entered in the cube size, the larger the size of the output file and thus the more processing power needed.


Boolean operations Group

Boolean Operations

The boolean operations are smart tools that ease the process of performing simple modeling tasks within SimLab Composer and without the need to go back to the cad design application.




- # **Union boolean operation:** removes the intersecting parts of objects or set of objects, while preserving the remaining part of the geometries.
- # **Difference boolean operation:** deducts the shape and volume of one object or set of objects from another object or set of objects.
- # **Intersrction boolean operation:** preserves the intersecting parts of two objects or set of objects, while removing the remaining part of the geometries.



Simlab Composer aims to simplify the 3D visualization process for the user, offering powerful and easy to use tools that can significantly improve the overall workflow, and allow the user to focus more on creativity rather than exhausting technicalities.

Material Menu

In this menu, the user needs to be able to apply materials for different objects in the 3D scene. Material task bar includes all the functions needed for material application, and materials management.




Material system tutorial:

Scene Group

Show Materials

This function button will display the Scene Materials dialog, which includes the material functions shown in the image below. Some of these functions are included the Material task bar, others are found only in this dialog.



Delete Material: This function deletes the selected material, from the Scene Materials dialog. In case the material is being used by objects in the scene, a dialog will appear asking the user to select a replacement material before the deletion.

Select Objects Using Material: This function selects all objects, in the scene using the selected material in the Scene Materials dialog. These objects-geometry will be highlighted in the Object Tree, and in the 3D area.

Apply Material To Selected Objects: To use this function the user should select object(s) first, then select a material from the Scene Materials dialog or the from the Material library. After that he can click this function button and the selected material will be applied to the selected objects.

- # Merge Identical Materials: In cases where more than one object in the 3D scene is using the same material, different copies of that material will appear in the Scene Materials window. This function cleans the materials dialog from unnecessary duplicates.
- # Change View: This display option is available for the user to change the way the materials are displayed, in the Scene Materials dialog. They can be displayed in Large, or Small icons, or can be shown as a list.
- # Sort by Name/Sort by Attributes: Two options for sorting the Scene Materials are available for the user.

Add New Material

This function creates a new default material-type, and adds it to the Scene Materials dialog. The new material with all of its properties will be shown in the Properties panel of the application Interface.

Delete Unused Materials

Deletes all materials not referenced by any object in the scene. This function is also found in the Scene Materials dialog.

Save as Library

After applying all materials for all geometry in a 3D scene, clicking this function will display the New Material Library window. In this window the user can input a name for the new library then click Ok. This will save the applied scene materials in a library, and it will be shown in the Current Library combo-box, and in the Manage Material Libraries panel.

Retain from Library

Before clicking this function button the user should first select the library to use, in the Current Library combo-box. This function will reapply materials included in the selected library to the different geometry based on previously assigned materials names.


Retain from Library


In cases where more than one object in the 3D scene is using the same material, Different copies of that material will appear in the Scene Materials window. This function merge the same materials copies on one copy of material.

Library Group

Regenerate Library

- **Current Library:** a menu list includes the default and user defined Material Libraries. Set to Composer as its default value. By selected the desired library, the library and its contents will appear in the Library panel.
- **Manage:** a button displays the Manage Material Libraries dialog box if clicked. In its dialog box, you can create new libraries, rename, delete, export, import, merge existing libraries. You can also create new groups in the selected Library, rename and delete them.
- **Regenerate Library:** a button, if clicked, will regenerate new icon/thumbnaill images for the content of the corresponding library, for display purpose only. A warning message appears.





Style Only

This toggle button allows you to turn on or turn off applying styles (including properties such as color, glossiness, alpha, etc.) when dragging-and-dropping a material from the Material Library onto a object in the 3D Area preserving texture information (including properties such as Texture, Bump, and Normal).



This is done by clicking the Style Only button in the Material tab before starting to drag any material.



You can turn on or off the this option by clicking over the Style Only button

Material Palette Group

Material Palette

SimLab Composer integration plugin is a great tool that allows you to create high quality renders for your design, and maintain a dynamic link where you can simultaneously adjust the model and instantly update the changes in SimLab Composer.



This great feature allows you to resume your progress using the dynamic link between cad software and SimLab Composer without any losses.


Save Material Palette

Material palettes is a useful feature that SimLab Composer provides, it can save your materials progress in a separate external file that can be reapplied easily.

Go to the material tool, and select save material palette, set the path and the name of the file and click save.

Reopen Cad Software and load the file you just saved. Go to the extension menu, then SimLab composer integration and select link with SimLab Composer.


As you can see the materials and textures applied in SimLab Composer, are the same materials applied in CAD Software.



Retain Material Palette

Retaining the scene materials option, allows you to keep any materials you applied to the design in SimLab Composer. not having this option toggled will re-import the original materials from CAD Software to the design.

Select the palette file that you previously save, and set the mode to material name




Material palettes is another useful feature that simlab composer provides, it can save your materials progress in a separate external file that can be reapplied easily.

UV Menu

UV


Texturing is the process of applying an image to a 3D object, to give it a more realistic look. Texture Coordinate menu gives the user different options to define the way the image is applied to an object.



Scene States Menu

Capture

Scene States enable users to capture different configurations for the selected 3D model(s), or for the whole scene. The User can check the properties to include in a scene state, from the Default Apply group in this tool. SimLab Composer's Scene States are smart in capturing attributes; they can include any combination of the listed attributes. This can be helpful in creating scene states for models with different attributes, and setups.



The user can also set the width and height for the scene state preview Image, to match the settings in the export template.

With the properties checked, the user needs to click the Capture option, to be either From Scene or From Selection. The first option will capture a scene state for the whole scene with the properties checked in the Default Apply group. The From Selection capture option captures a scene state for the selected model(s), with the checked properties. Depending on the checked properties, the generated scene state will be added to the corresponding tab(s) in the Scene States library.

Library

A button, if clicked, will regenerate new icon/thumbnail images for the content of the corresponding library, for display purpose only. A warning message appears.

The Regenerate option will generate a rendered preview image for the selected scene state, with the size specified in the Preview Image group. The Regenerate All option, will generates rendered preview images for all the scene states.

Scene states have many useful applications including;


Manage

- a button displays the Manage Material Libraries dialog box if clicked. In its dialog box, you can create new group, remove group, rename group. You can also move groups up and down.




• To Create a Scene States, Follow the steps below:


1. Open the Simlab Composer.
2. Import the model which you want to make Scene State on it.
3. Now, click [Materials Library](#) in [Navigation Panel](#) to view all materials in the library, then drag-and-drop desired material on the model.
4. Select the object and click **Scene States** → **Capture**, the **Scene State dialog** will appear.



5. In the dialog above, select **Materials State** then click **Capture From Selection**, now the state will appear in the [Scene States library](#) in [Navigator Panel](#), you can edit the state in [Properties Panel](#) below by one click on it.



6. Repeat 3 and 4 steps to add more states, to show the state on the model click double on any state in [Scene States library](#) .






Also you can find a video tutorial to Create Scene States below.



Render Menu

SimLab Composer Real Time renderer (SimLab RT) is a powerful, fast, and easy to use real time renderer; that has full integration with SimLab Composer. The renderer is optimally parallelized, so it can take advantage of all the CPUs available in the machine.



SimLab RT renderer is suitable for MCAD, interior rendering, producing top quality rendered images. To learn more about SimLab RT renderer, click Help in the Setting/Help menu, and select Render Help.

Thanks to HDR Light Studio for providing us with high quality HDR images included in SimLab Composer.

We released a new ISPC renderer for MaxOS

Rendering menu provides the user with all tasks necessary to create professional high quality rendered images/movies.



In the tutorial video below, we will show you how to importing a 3D model to SimLab Composer, then shows how to assign materials, After that the tutorial teaches how to utilize rendering capabilities of SimLab Composer



Interactive Group

Real-time View

Clicking this function will start real time rendering for the 3D scene, using the parameters in Render Settings. The function short-cut is F4, and RT rendering can be stopped by un-toggling the Real Time function button or pressing F4.

Real-time Clay Mode


This function starts real time rendering in clay mode. Which is a real time rendering mode used for viewing the effect of lights in scenes, by changing all materials, except glass and emitter materials, to gray matt.



Fixed Group


Render Fixed Size

This function starts real time rendering for the 3D scene, with a fixed image size. The image size used will be the one set in the Output Image task.



Render Fixed Clay Size

This function starts real time rendering in clay mode. Which is a real time rendering mode used for viewing the effect of lights in scenes, by changing all materials, except glass and emitter materials, to gray matt.



To File Group

Render to File

This type of rendering is time limited, with a fixed image size, as in Fixed-Render. The value to end/limit rendering time is SPP (Sample per Pixel) value. This value can be found in Render Settings under the Output Image task.

A limited time rendering is automatically used by Animation Rendering, Scene States Rendering, and Render to File.

Render Clay to File

This type of rendering is time limited, with a fixed image size, as in Clay Fixed-Render. The value to end/limit rendering time is SPP (Sample per Pixel) value. This value can be found in Render Settings under the Output Image task.

A limited time rendering is automatically used by Animation Rendering, Scene States Rendering, and Render to File.

Animation Render

In a 3D scene with animation defined, clicking Animation function will start rendering animation. Animation rendering is a limited time rendering, from the From Frame to the To Frame set in the corresponding spin-boxes, in the same task.

Sun Study

This is useful for landscape designers, architects and interior designers. Simply from the render menu, the user selects Sun study, then defines the initial and final sun states.



The study shows the sun and shadow states for the scene.

Scene States

For 3D scenes with scene states this function will start consecutive rendering for the scene states defined in the scene. Manage Scene States dialog will appear for the user to check the scene states to render, and the order of rendering. Clicking Ok will start limited time rendering based on the SPP value.

VR Based Animation Rendering

Rendering is a complex process that generates very realistic images, rendered images in many cases cannot be distinguished from photos. Performing complex rendering consumes a significant amount of time.

Users interested in previewing their work quickly, have a great new option in Composer 9. VR based rendering gives users great images in a very short amount of time, This is great for multi-iterations, until the user is ready for the final animation render, for some users this may be the final animation render they need.




VR based animation rendering demo video.




Package Group

Package Render

Distribute rendering is supported in SimLab Composer. It allows the user to distribute rendering of complex animations, among a number of machines. With the animation '*.sim' file opened click Distribute function to open Distribute Render Animation dialog.




Fill in the required settings, and then click the Generate Rendering Packages button. The output folder containing the packages will open, since the Open containing folder option was checked in the dialog.



A number of (*.srd) files equivalent to the number of machines input in the dialog, will be saved in the output folder.

Copy each file to a rendering machine that has SimLab Composer already installed. Click the Render function, in the Package group, to open its dialog. Browse to the rendering package (*.srd) file, and select the output folder. Check the Open output folder option, and then click Start Rendering. A rendering animation progress bar will continue to appear along with rendering menus until the animation rendering is done.




Setting Group

Environments Settings

3D scenes require some sort of lighting, to give 3D scenes/models a more realistic look. Environments for rendering in SimLab RT can get lighting from HDR, from Sun, or from lights and emitters defined in the scene. The user has the option mix and match between these light sources. This can be done by enabling the HDR and the Sun each from its Render Settings dialog; this dialog has four tabs, described below;

HDR Environment




Clicking the HDR option will display its render Settings in the properties panel. HDR is the easiest method for achieving photo realistic views of MCAD, and studio shots of a product, HDR's are files of types (*.hdr) or (*.exr). Environment images are applied as a sphere surrounding the 3D scene. They include light sources that are automatically used when rendering the 3D Scene.

To select an HDR file click the environment settings in the render menu. This will open a windows dialog where the user can browse to the HDR file to use. Or just double click an HDR image from the library panel, to display the selected HDR, the user needs to make sure that the background is set to Environment.

The color and brightness of the HDR image can be adjusted in the render settings dialog, and the new settings will automatically be saved and applied. The user can also rotate the environment image, by adjusting its slider in the render settings dialog. SimLab Composer provides a number of HDR environment images, free and commercial environment images can be used to extend the SimLab Composer selection of environment images.

Sun Environment



This environment setting simulates physical sky at different sun angles (Solar Elevation), which determines the time of the day. The sliders of the parameters of this environment option, makes it easy for the user to view the effect of each parameter, in real time. The user can select to Enable Sun, in the render settings, in addition to enabling the HDR.

The user has multiple parameters to control the sky:


- # Albedo: This parameter controls the effect of ground color reflection, which in turn affects the color and feel of the sky.
- # Turbidity: This parameter affects the clarity of the sky.
- # Solar Horizontal Angle: This parameter sets the rotation of the sun around the zenith.

Users not comfortable with specifying numerical values for Solar Elevation, and Solar Horizontal Angle, can add Sun Light for the Light toolbar. Changing the direction of the sun, using its draggers, and then clicking the accept mark; will update the values in these two fields, if the Sun is selected as the light source.

Sky Strength and Sun Strength: These two parameters can be used to increase/decrease the sky/sun strength effect on the rendered image. More details about rendering parameters can be found in Renderer Help, under the Help menu in the Settings/Help Bar of the application interface.

Render Solar Disc: This check box option, when checked, will show the solar disc in the rendered image.

Ground




When setting the environment light source for rendering, the user has options for adding ground shadow and/or ground reflection to the 2D ground:

Ground Shadow: When clicked, its Render Settings will appear in the Tree/Task Panel. This option will generate shadows on the ground, and the user can select the color and strength of the generated shadows. To apply the shadow settings to rendering, the user needs to check the Enable Ground Shadow option.

Ground Reflection: Turns the ground into a reflective plane, where the user controls reflection color, roughness, and strength. The Enable Fresnel option determines whether fresnel reflections are enabled or disabled. To simulate metallic looking reflections, Fresnel reflections should be disabled. Environment Reflection option, reflects the scene's environment when checked.

To apply the reflection settings to rendering, the user needs to check the Enable Ground Reflection option.

Background



The background for rendering can be one of four options;

From Environment: Selecting this background option will apply Environment settings to the rendering background.

Single Color: With this background option the user can select a color to use for the background of the rendered image.

Background Image: This background setting option requires the user to browse to an image file to be used for the background of the rendered image.

Spherical Background: enables the user to select (*.hdr), (*.exr), or any image file, that will be wrapped around a sphere or hemisphere, and select color, size and brightness. This option is added to give users more control since the Environment-HDR (global HDR) in the Render Settings dialog can be rotated, but cannot be scaled.

Advanced Render Settings

In this panel the user can set the main rendering parameters.

Rendering modes: SimLab Composer provides four types of rendering modes:


- Fast Path Tracer.
- MIS Path Tracer.
- Interior Renderer.
- Element Renderer.

Render Max Depth: is the number of ray bounces of the light. Increasing the number of ray bounces improves lighting for complex scenes, especially diamond and glass scenes, but it slows rendering.

Automatic locking Time (seconds); is the time in seconds after which the image will be locked for navigation, in case of Real Time View rendering. Setting this value to Zero will disable automatic locking.

Image ratio during navigation; is the ratio of the rendered image dimensions to use while navigating the scene.

Number of cores to be ignored; is the number of CPU cores not be used by the renderer. This is helpful when the user is working on other applications while rendering. Setting this parameter to 0 will use all cores for rendering.



Rendering Mode

Fast Path Tracer

MIS Path Tracer

Interior Renderer

Light Depth

Specular Depth

Element Renderer

Settings related to the functionality of Interior Renderer Mode:

1. Light Depth: Set the amount of light energy.
2. Specular Depth: Control the visual appearance of specular reflections. It represents the amount of specular reflectivity a surface has.




The default values for both of Light Depth and Specular Depth (which is "3") are good and commonly used. Don't change this unless you really know what you're doing.

Output Image Tab

In this task bar the user can select the format for the output image and its dimensions.

The properties panel will display Render Settings dialog. In this dialog the user can input the base file name, the output folder, and SPP to limit the rendering. The open containing folder check option will open the output folder after finishing rendering.



Region Rendering

Region Rendering

It allows the user to check complex parts of the scene and see how they look like early in the rendering process, Using a small area of the scene to determine the needed SPP for the scene.

Focusing rendering power in small areas that need more rendering to finish the process fast.




Region Rendering:



Image Effect Menu

SimLab Composer provides its users with image post processing capabilities. Any combinations of image effects can be applied to a rendered image. In this task the Tree/Task panel will display the Render Settings for the image.



Vignetting

This effect is a reduction of an image's brightness/saturation, at the periphery of the image compared to its center.

Gray Scale

This effect renders the image in gray scale.

Edges

This effect renders the current model with edges shown.

Blooming

A glow added to the rendered image. The user can change the Blur Radius, Brightness, and Opacity for this effect.

Cool, Warm and Saturation

These image effects can be applied by setting a delta value, and they can be applied exclusively.



Texture Baking Workbench

Texture Baking workbench dedicated to bake textures of your 3Ds. Simply, Texture baking is the process of storing rendering results as textures.



Texture Baking, or Rendering to Texture, allows you to create texture maps based on an object's appearance in the rendered scene. The textures are then baked into the object that is, they become part of the object via mapping, and can be used to display the textured object rapidly on 3D devices such as graphics display cards or game engines.

In other words, baked textures are those that have the highlights, shadows, and shading built into the texture. It would have the highlight of the body built into the texture so it appears to be more natural or realistic looking. Therefore, it is possible to use rendering algorithms in SimLab Composer to simulate shading, shadows and bumps on the surface (or texture) of a 3D object. This process is commonly referred to as "baking" the texture. Texture baking refers to the calculation of environmental information (lights, shadows, etc) and rendering that information as a texture than can be used to make more realistic looking.




Baking Menu

Baking Menu

This menu in the texture baking workbench, offers you the ability to use the smart baking system:

- **Smart Bake:** Which is a tool that uses advanced calculations and algorithms that negate the effect of having a flipped object's normal. while conventional texture baking softwares requires all the face normals to be displayed properly for the baking process to workout, SimLab Composer's smart baking offers you a smart solution to bypass that demanding step.
- **Object(s) Bake:** which is similar to the traditional baking and will produce texture maps according to the face normals of the objects.



**By clicking the Smart Bake button, the Texture Baking Setting dialog box appears (as shown in the following image), the following options can be found in the Texture Baking Setting dialog box:

Texture Size:

Min: list menu 16, 32, 64, 128, 256, 512, 1024, 2048, or 4096 (in pixels).

Max: list menu 16, 32, 64, 128, 256, 512, 1024, 2048, or 4096 (in pixels).

Baking Quality:


Sample Per Pixel (SPP): controls the quality of the texture baking.

Dynamic Update (in SPP): controls at which rate should the texture baking results appear during the baking process.


Geometry Processing: fast or Top Quality

Optimize Baking Time: checkbox:

Polygons Per Object Limit: enter the number of ...



After confirming the baking settings by pressing OK, a progress box (as shown in the following image.) appears to reflect baking progress for each object being baked in addition to the overall progress. Clicking the Next Object button will skip baking progress for the current object.




Baking Tools Menu

Baking Tools

Show Baking group consist of the following:

- **Clean:** you can clean the model of any baked texture.
- **Break Geometry:** you can break the objects to faces or to geometries.
- **Break Faces:** to break the selected 3D model into its faces. Each face will be converted to an geometry and appended to the Object Tree.
- **Merge on Material:** with an assembly selected in the 3D Area or Object Tree, this tool will merge geometries that have the same material into a single geometry.
- **Flip Normals:** will reverses the face normals of an object in case the users wants to manually control the objects normals.
- **Info:** displays important information such as the number of selected objects, and the number of vertices and polygons in a model.




Keep in mind that in baking, the material normals (which affect how light appears to reflect from the model's surface) can be recorded -- this results in very specialized images with RGB values based on normal vectors.

Show Baked Menu

Show Baking


The show group contain a single task:

- **Show Baked:** this option will switch the view between the regular model and the textured bake model.



Animation Workbench


The animation workbench in SimLab Composer offers multiple tools that facilitate animating objects and cameras in the 3D scene. The animation tools allow you animate objects and cameras, they also provide a way to create videos and movies as well as walk-throughs.



Remember that the animation time line is activated.

The time line is a dynamic diagram that holds editable keys denoting any animation created in the scene. You can also notice that the animation time line is activated, the time line is a dynamic diagram that holds editable keys denoting any animation created in the scene.

Additionally, SimLab Composer can produce an image sequence of the animation and is able to convert the sequence to a video file that can be easily viewed externally.



Animation video tutorial:

Simlab Composer

Mechanical Animation




Mechanical Training Series
Part 6

 SimlabSoft

Object Menu


The object's animation menu holds several tools associated with animating an object, those presets assist the user in creating common object's animation quickly and efficiently.



Object Animation Group

Show/Hide Object Animation


Selecting a 3D object at any frame other than zero and clicking Hide from Object Animation group, will add a key frame at that location and the object will be hidden there. Another key frame will be added at frame zero, with the object shown. Using these two functions hide/show animations can be created easily.



Round Table

Round Table Object animation rotates the selected object by default, 360 degrees around the global z axis. The animation starts at frame 0 and ends at the last specified frame. Selecting the green animation line of the object, in the Time Line, will display the animation parameters in the properties panel of the application interface, as shown in the image below.


The user can select to change the Start/End frames, as well as the angle of rotation.



Wheel Animation


Wheel Animation is useful for rotating object(s) around a selected axis. To create wheel animation the user needs to select the object(s) to be rotated, then to click this function button. In the image shown below one of the loader's tires were selected. To be able to precisely select the wheel's center, change the pick mode to Pick Center of Curvature. This will generate edges for the whole scene and will select the center of the selected curvature precisely. The wheel animation dialog will appear where the user can set the animation parameters.

Select the start frame for the animation, the end frame and the number of revolutions. Number of revolutions is the number of full rotations to be done by the selected object(s). The user can also select the rotation direction to be Clockwise or Counter Clockwise the direction is determined using the right hand rule around the rotation axis, always points out of the geometry.



Click Pick Center, and select the circle of the tire. The normal of the circle's center will be highlighted, click the approve icon to end the process. As can be seen in the image, an animation line for the Tier has been added to the time line.

Selecting this green line will display wheel animation parameters, in the Properties Panel of SimLab Composer interface. The user can change the Start and End frames for the animation, as well as the angle of rotation. In the Wheel Animation dialog shown above, the Number of Revolutions was set to 10. This will result in $10 * 360 = 3,600$ angle of rotation.



Following the same steps, the user can create wheel animations to the other three tires of the loader.

Follow Path

Path animation can be used to make an object follow a predefined path. This object can be a 3D object, a camera or a light in the scene.

Path Animation ? X

Begin Frame 0 End Frame 100

Constant Speed Duration


From 0 To 100

Pick Path Cancel

Material Animation Group

Movie Textures are animated textures that are created from a video file, they can be applied to objects while being in the Animation workbench.

To add an animated texture, you have at first to select an object then click above the Movie button. The Material Animation dialog box appears (as shown in the following image) asking the user to specify a movie and to enter inputs as desired.



The Material Animation dialog box consists of the following fields and buttons:


- **Movie:** Browse and select the desired movie from your disk drive.
- **Movie Length:** Enter the length of the movie (in seconds). This displays the the first n seconds of the selected movie.
- **Begin Frame:** Determine the frame where you would like to start showing the texture in animation timeline.
- **End Frame:** Determine the frame where you would like to finish showing the texture in animation time line.
- **OK:** Confirm and accept settings.
- **Cancel:** To abort the operation.



Supported file types are MP4, avi, or flv.

Camera Menu

In this Panel the user can create key frames camera animations, as well as use predefined camera animation functions.




Camera Animation Group

Capture Camera

Captures the current view in the 3D area with an animated camera, and creates a key frame at the current location on the animation TimeLine.

Round Table

This function creates a camera animation, for the whole scene, that rotates 360 degrees around the global Z axis. By default this animation starts at frame 0 and ends at the last frame of the animation.




Helical

Creates an animation that rotates the camera 360 degrees around the global Z axis, with translation from the current elevation of the camera to the ground ($Z = 0$), suitable for showing high buildings.


Director Record

Director Camera gives the user the ability to create animations that combine views from multiple animated cameras/views, in a scene. Clicking the Director Record button will create a new camera named director camera and adds it to the Object Tree. The director camera will start recording the views from the existing camera in the active view.



Video Menu

The video's menu enables the user to capture from view, create videos .



Video Group



Create from View

This function can be used to share animations created in SimLab Composer with others. The Viewer Video Export dialog will open, where the user can select the frames to include in the generated video/images, or check the Full Animation option.




If the Generate Video option is not checked clicking the Create button will generate images, for all the selected key frames, in the render output folder. When the Generate Video option is checked, video will be created using another application for creating videos.

If the Generate Video option is checked the user can choose an audio file to add to the generated movie. The video quality, frame rate, and output formats can also be set in this dialog.



Movie Maker

This function can be used to create videos of several output formats from sequential render images using the movie maker tool. The Viewer SimLab Composer Movie maker dialog will open, where the user can select the frames to include in the generated video, it also adds audio files to the generated movies.



Walk-through Menu

The last tool available in the animation workbench, is the walk-through tool.

A Walk-through is a type of animation that mimics a human walking around within the 3d scene, which with its varied options, offers accurate control over the camera's movement that immensely improves your model's demonstration.



Walk-through in SimLab Composer differs from the Path Animation, where Walk-through don't require defining a path of the walk by drawing a line, or assigning the camera to the path. In SimLab Composer, the term of a Walk-through isn't a camera that follows a path that you define.



Walk-Through tutorial:

Walk-through Group


Walkthrough

In this part of SimLab Composer interface, the user can create and record full motion video tours of a location. Essentially, creating an animated walkthrough with SimLab Composer is a four step process.

The steps for creating a Walkthrough are simplified as follows:

1. Start and set walkthrough parameters
2. Go on Tour
3. Configure the Time
4. Render the Animation

Each of these steps is covered later in this section.



- Start: The button allows you to open the Walk-through Parameters dialog box. This group of parameters controls dimensions and behavior of the camera measured in meter, m/s, or rad/s, which you can set to define and describe the characteristics of the camera object that you will take on while being in the scene.

- Stop: When you are done with the tour in your scene, click over the Stop button in order to exit walk-through mode and return the normal navigation mode for your scene.
- Reset: This button allows you to reset the walk-through to its origins represented only in the initial start location and the initial orientation.



The Walk-through feature includes several keystrokes for controlling the camera's movement. The arrow keys move the camera forward, left, back, and right. You can also use the Z and X keys to rotate the camera left and right. Pressing the Z or X keys while the camera is moving changes the direction in which the camera points.

Walkthrough Parameters:

This panel is located at the rightmost on the Walk-through icon. You find the following buttons in the Walk-through panel, as shown in the following image:

- a. Height: Set your length in meters, this value presents the length of your body that affects. In the scene, this affects your proceeding when you encounter a low ceiling.
- b. Width: Select your width in meters, this value presents the width of your body. In the scene, this affects your proceeding when you encounter a gap between two close objects.
- c. Movement Speed: Determine your movement speed in m/s (Meters Per Second). The higher value you assign, the faster you move.
- d. Rotational Speed: Specify your rotation speed in rad/s (Radians Per Second).
- e. Step Height: Set the height of your steps in meters while walking in the scene, this value shows the maximum object's height that you can climb in scene.
- f. Create New Camera: You can select this checkbox to create a new camera to be dedicated to Walk-through, or leave it unselected to use the Active Camera. Walkthrough can be performed using the Active Camera or a new created camera.
- g. Pick: Complete the dialog box and click the Pick button to accept the current settings. After the dialog box is closed, you'll have to pick the start location and direction.
- h. Cancel: Click Cancel to abort task. This closes the dialog box without any changes.

Walkthrough Parameters

Height: 1.5 meter

Width: 0.4 meter

Movement Speed: 1.40 m/s

Rotational Speed: 0.03 rad/s

Step Height: 0.35 meter

Create new camera

Pick Cancel

Once you deploy the camera, the overall settings will be applied. A mode is enabled in which you can control the camera using the keyboard. Walk-through feature moves through the scene like a first-person video game where collision detection is also enabled, how cool is that!



Beware of falling! Always ensures that the feet stay parallel to the ground or an object's surface at all times and can be used to walk over soft or rough terrain. If that happened, just click the Reset button.



Cannot see your scene! Always, keep a logical ratio between the size of the camera and scene itself.




Hiding an object in the scene does not disable collision with that object during walk-through.

Walk-through Library

The Walkthrough library is where scene states are stored, they appear as thumbnail images. To store a scene state, you need to select Capture button from the Walkthrough panel.

Capture: A newly added button (as shown in the following image) to the Walkthrough panel. It is used to capture a scene state of the current active walkthrough.



The toolbar of the Walkthrough library consists of the following buttons, as shown in the following image:



Delete: To erase the select scene state from the Walkthrough library.

Delete All: To erase all scene states from the Walkthrough library.


In order to restore the 3D Area to the captured scene state, the user has two ways to do that:

- Double clicking an image thumbnail in the Walkthrough library.

- Dragging-and-dropping an image thumbnail into the 3D Area.

This will result in transforming the camera to match the scene state stored in it.

as shown in the following image a Walkthrough library that contains five captured scene states.




Speed Group

Speed:

Speed Group is located next to the Work-through group and displays the speed associated with the active walkthrough. You can change the speed of the motion anytime with this toolbar.

Here is a closer look at the Movement Speed Toolbar that includes only one graphical control element, as shown in the following image:




- Movement Speed: This horizontal slider lets you set or adjust a value by moving an indicator. This control is a horizontal slider with a handle that can be moved right and left on a bar to select a value. The bar allows you to make adjustments to the Movement Speed value throughout a range of allowed values. It allows you to alter the movement speed while being in the scene by decreasing it through dragging to the left (Slower) or increasing it through dragging to the opposite direction (Faster).


Animation Recording Group

Recording:

In this group, two buttons are displayed to start and stop recording from the Graphical User Interface (GUI), as shown in the following image. The Record toolbar provides flexible options to start and stop recorder associated with the active walk-through and depending on your set up:




- Start: Recording starts when you click the Start button. Use this button to manually start the recording.
- Stop: To stop recording, click Stop button. You can always stop recorder manually. When you click Stop, a dialog box appears with the following parameters (as shown in the following image):
 1. Starting frame: Specify the number of the frame where you want the animation starts from.
 2. FPS (Frames per second): Determine the Frame Rate in which to produce unique consecutive images.
 3. Stop walk-through mode: A checkbox option enforces you to exit walk-through mode back to the Active Camera once Save button is clicked.
 4. Save: Save the recording settings
 5. Discard: Reject last recording session.




Capture to Library Group

Capture to Library:

The Walkthrough library is where scene states are stored, they appear as thumbnail images. To store a scene state, you need to select Capture button from the Walkthrough panel.



• **Capture:** A newly added button (as shown in the following image) to the Walkthrough panel. It is used to capture a scene state of the current active walkthrough.



The Panel of the Walkthrough library consists of the following buttons, as shown in the following image:

Delete: To erase the select scene state from the Walkthrough library.

Delete All: To erase all scene states from the Walkthrough library.




In order to restore the 3D Area to the captured scene state, the user has two ways to do that:

- Double clicking an image thumbnail in the Walkthrough library.
- Dragging-and-dropping an image thumbnail into the 3D Area.

This will result in transforming the camera to match the scene state stored in it.

Animation Timeline

Time Line provides the user with a tool to visualize and edit animation key frames. The time line is displayed by default in the Library panel of the Animation workbench. Click the Show/Hide details button in the top right part of the time line, to show or hide the timeline details.




In the timeline the user can also set the animation duration, by setting the end key frame value.


The current frame is marked on the time line by a red vertical line. The names of the animated objects appear on the left part of the time line, clicking on the name of any object automatically selects it in the 3D area.

The current frame is marked on the time line by a red vertical line. The names of the animated objects appear on the left part of the time line, clicking on the name of any object automatically selects it in the 3D area.


The user can play animation by clicking the Play Animation button in the animation time line, or by hitting the Space Bar. The tool bar also includes the tool buttons Go to First Frame (Shortcut Home) and Go to Last Frame (Shortcut End).



1. Capture Key frame for Object
2. Capture Key frame for Camera (Ctrl+K)
3. Director Record button, which can be used for managing animations from multiple cameras
4. Go to Previous Animation Key Frame of the Selected Entity
5. Go to Next Animation Key frame of the Selected Entity
6. Select All Key frame on Animation Time-line
7. Copy and move selected key frames
8. Move selected key frames
9. Delete selected key frames
10. Delete all animations



11. Create an [Animation Sequence](#)
12. Show animation sequence list



- 13. Forward Play/Pause (Space)
- 14. Go to Last Frame of Working Area (End)
- 15. Backward Play/Pause (Ctrl+Space)
- 16. Go to First Frame of Working Area (Home)
- 17. Working Area Start
- 18. Current Time
- 19. Working Area End
- 20. Scale Time Line

Animation Properties:


Clicking on an animation key frame on the time line will show its properties, in the Properties panel. The user can change these properties, for different types of animation.

The user can also change the location of any key frame on the time line, by selecting then dragging it from a location to another.


Animation Auto Ease Options

Animation Auto Ease Options:

- The auto ease options specifies the speed curve of an animation.
- SimLab composer comes with various predefined motions, a motion is type of composer generated animation that is used for creating predefined animations such as round table, follow path wheel motions for selected object and round table and helical motions for cameras.



- (1) Regular Keyframe
- (2) Selected keyframe (appears in blue)
- (3) Previous keyframe
- (4) Next keyframe





- (1) Regular keyframe
- (2) Predefined keyframe
- (3) Previous keyframe
- (4) Next keyframe
- (5) Selected Keyframe (appears in blue)
- (6) Start frame
- (7) End frame


Regular keyframes:

- SimLab composer presents three types of ease that automatically adjusts the influence into and out of a key frame to smooth out sudden changes in translation, rotation and scale. these options are auto ease out, out ease in and auto ease. with these options users can ease speed of an object when coming into or out of a key frame or both, where (auto ease out) is used is to ease speed coming out of a selected key frame, (auto ease in) is used to a speed coming in to a selected key frame, and (ease) is used to a speed coming both into and out of a selected key frame.

- With animation ease options, you can easily achieve smoother and more realistic motion for geometries and camera in your 3D scenes.

Possible symbols for regular with and without ease effect:

Icons	Description
	<p>No Ease</p> <ul style="list-style-type: none">• Regular animation keyframe without any ease type applied• Maintain constant speed at the keyframe itself from the direction of previous keyframe.• Maintain constant speed from the keyframe itself to the direction of next keyframe
	<p>Ease out</p> <ul style="list-style-type: none">• Regular animation keyframe with ease out applied• Acceleration• Maintain constant speed at the keyframe itself from the direction of previous keyframe.• Accelerate (speed up or increase speed) from the keyframe itself to the direction of next keyframe.
	<p>Ease in</p> <p>Deceleration Regular animation keyframe Decelerate (slowdown or decrease speed) at the keyframe itself to the direction of previous keyframe. Maintain constant speed from the keyframe itself to the direction of next keyframe</p>
	<p>Ease</p> <p>Deceleration then acceleration Regular animation keyframe Decelerate (slowdown or decrease speed) at the keyframe itself to the direction of previous keyframe. Accelerate (speed up or increase speed) from the keyframe itself to the direction of next keyframe.</p>



In the image above, The darker the red gradient color, the faster the object is.

- The first keyframe of Box 2 has a speed of 0 with an influence of 100% on its right side. Auto Ease Out automatically adjusts the influence out of a keyframe. The object gradually accelerates as it leaves first keyframe until it reaches last keyframe, where it reaches its maximum speed. Keep in mind that Auto Ease Out requires an existing next keyframe in order to take effect.
- The first keyframe of Box 3 has a speed of 0 with an influence of 100% on its left side. Auto Ease In automatically adjusts the influence into a keyframe. The object starts at its maximum speed and slows down as it approaches last keyframe. Keep in mind that Auto Ease In requires an existing previous keyframe in order to take effect
- Both of first and last keyframes of Box 4 have a speed of 0 with an influence of 50% on right side of first frame and left side of last frame. This automatically adjusts the speed of change, where accelerates as animation retreats from the first keyframe until it reaches maximum speed at frame number 10 and from there decelerates as animation advances toward the last keyframe.
- The middle keyframe of Box 5 as a speed of 0 with an influence of 50% on both sides. The object slows down as it approaches middle keyframe, and gradually accelerates as it leaves. Keep in mind that Auto Ease requires existing previous and next keyframes in order to take effect on both sides of selected keyframe.

Predefined Motions:

- SimLab Composer comes with various predefined motions.

- A Motion is a type of Composer-generated animation that is used for creating predefined animations such as Round Table, Follow Path, Wheel motions for selected object, and Round table and helical motions for cameras.

- In case of predefined motions, start and end frames have a speed of 0 with a default influence of 25% on sides that falls within an animation sequence itself.




- The symbol of predefined motion provides a simple visual representation that indicates the relative speed at each particular frame within it.


• Possible parts of predefined symbols with one of ease effects:

The symbol of predefined motion on the animation time-line consists of:

- The animation sequence itself
- Start frame, which acts as a regular keyframe
- End frame, which also acts as another regular keyframe

Possible symbols for redefined keyframes with and without ease effect:

Icons	Description
	<p>No Ease</p> <ul style="list-style-type: none"> • Start frame of a predefined animation keyframe • Maintain constant speed at the first frame of the keyframe itself from the direction of previous keyframe. • Maintain constant speed from the first frame of the keyframe itself to the direction of the end frame of the keyframe itself.
	<p>No Ease</p> <ul style="list-style-type: none"> • Predefined animation keyframe • End frame of a predefined animation keyframe • Maintain constant speed at the end frame of the keyframe itself from the direction of the first frame of the keyframe itself. • Maintain constant speed from the end frame of the keyframe itself to the direction of the next keyframe.
	<p>Ease Out Acceleration</p> <ul style="list-style-type: none"> • Start frame of a predefined animation keyframe • Maintain constant speed at the first frame of the keyframe itself from the direction of previous keyframe. • Accelerate (speed up or increase speed) from the first frame of the keyframe itself to the direction of the end frame of the keyframe itself.



Ease in Deceleration

- End frame of a predefined animation keyframe
- Decelerate (slowdown or decrease speed) at the end frame of the keyframe itself from the direction of the first frame of the keyframe itself.
- Maintain constant speed from the end frame of the keyframe itself to the direction of the next keyframe.



Ease in Deceleration

- Start frame of a predefined animation keyframe
- Decelerate (slowdown or decrease speed) at the first frame of the keyframe itself from the direction of previous keyframe.
- Maintain constant speed from the first frame of the keyframe itself to the direction of the end frame of the keyframe itself.




Ease out Acceleration

- End frame of a predefined animation keyframe
- Maintain constant speed at the end frame of the keyframe itself from the direction of the first frame of the keyframe itself.
- Accelerate (speed up or increase speed) from the end frame of the keyframe itself to the direction of next keyframe.




Ease Deceleration then acceleration

- Start frame of a predefined animation keyframe
- Decelerate (slowdown or decrease speed) at the start frame of keyframe itself from the direction of previous keyframe.
- Accelerate (speed up or increase speed) from the start frame of the keyframe itself to the direction of end frame of the keyframe itself.



Ease Deceleration then acceleration


- End frame of a predefined animation keyframe
- Decelerate (slowdown or decrease speed) at the end frame of the keyframe itself from the direction of the start frame of the keyframe itself.
- Accelerate (speed up or increase speed) from the end frame of the keyframe itself to the direction of next keyframe.



- Box 1 has predefined motion with no ease effects
- Box 2 has predefined motion with ease out only.
- Box 3 has predefined motion with ease in only.
- Box 4 has predefined motion with ease out and ease in effects.




In the tutorial video below, we will show you how to use an animation auto ease types:




Sequence Timeline

An additional essential feature that Simlab Composer offers is creating animation sequences.

To create interactive sequences that can be implemented in the VR experience in the Simlab viewer. Go to the animation Tab to reveal the time line where we are going to manage the animation keyframes and sequences.



Click on the “create sequence” icon, then Select the created key frames and Type in the name of the sequence and click “ok”.




To create different animation scene sequence simply switch the created keyframes to reverse the animation.



In this dialogue will appear inquiring whether you want to delete the keyframes from the timeline after the sequence creation.




Note that you can view the created sequences by switching to the sequences tab in the bottom panel, or by clicking on "Show Animation Sequence List".



Show Animation Sequence List will appear, as you show in the image below:

- Show as animation: If you delete the keyframe from the timeline, by clicking on this button you can return the keyframe again on the timeline.
- Delete: To erase the selected sequence from the library.
- Manage Groups: The Manage groups button launches the Manage groups dialog box o give the user options to create, delete and rename Sequence groups.





Create Animation Sequences for VR:




Simulation Workbench

The Simulation Workbench can be available and accessed based on the acquired license. If you have already purchased the corresponding license, you can find this workbench on the Workbenches Bar within SimLab Composer GUI (For more information about "Ordering and License", see related section later in this manual).



You can now use SimLab Composer 2015 (SP1) to model the behaviors of objects in 3-D space. Thanks to its powerful physics engine that allows simulation of the way bodies of many types are affected by a variety of physical stimuli, provided to simulate physical systems such as Rigid-Body Dynamics in real-time and considering collision detection. The Simulation Workbench is dedicated for executing physical and mechanical simulations within SimLab Composer application. It is designed in such a way that helps you easily create and simulate complex mechanisms which can be imported from various file formats supported by SimLab Composer.

as shown in the following image the workspace of the Simulation Workbench when the Solids panel is active by default. The workspace presents the Simulation toolbar, the Geometries Tree, Solids Tree, and the Links Tree. The Simulation toolbar is placed at the top of the application window that displays a large collection of commands in a visual layout through a tabbed interface, the Geometries Tree is placed on the left-side, while the Solids Tree is grouped with the Links Tree on the right-side.



The Geometries Tree only appears when the Solids Tab is selected.

The Simulation Tool composed of four menus, use these menus to navigate and switch among the sets of widgets. Solids are defined in the Solids menu. In the Links menu, solids properties and relationships between each other are set. Finally, the simulation is controlled and performed in the Simulation and interactive menu:

1. Solids menu: Geometries are defined and classified, where each solid contains either one geometry or a group of geometries.
2. Links menu: Properties of solids and relationships between each other are set.
3. Simulation menu: Where simulation is controlled and executed.
4. Interactive menu: to allow the user to control machines using a Keyboard, or a Joystick..



Simulation video Tutorial:



Solid Menu

The first step in creating a simulation is converting your 3d design to solid parts that can be physically simulated, to do so, you can either manually select the parts and convert them to solid, or you can click on "auto detect solids" and simlab composer will automatically detect the objects in your scene and convert them to solids.




Keep in mind that the first step in every simulation project is to define and create solids from the original geometries of your model.

The Solids Panel contains the following Menu, as shown in the following image:

- Auto Detect Solids
- Solid Creation
- Appearance

Each of these Menu is covered in the following sections.





The Geometries Tree and the Models Library are associated with the Solids Tab. Once the Solids Tab is activated, they will be displayed on the left-side and bottom of the application window, respectively.



Solids detection or creation is considered as a transitional stage. Therefore, solids and links properties are not editable while you are activating the solids menu.


Auto Detection Group

Auto Detect solids:

• Detect: You can take advantage of this helpful button for automatic detection for solids, this gadget is based on running a complex mechanism that automatically define and classify a model's geometries and assemblies into solids, where each solid contains either one geometry/assembly or a group of geometries/assemblies.

The Auto Detect button helps the user automatically identify the solids in the model by running an algorithm that creates solids based on the objects and geometries present

As shown in the following image the simulation workspace with an imported model before clicking the Detect button, where the Geometries Tree on the left shows the original geometries of the objects in the model, and the Solids Tree on the right shows the created solids. Here, the Solids Tree is still empty because there is no solids created yet.





If the imported model is from an analytical file format like .STEP, this algorithm makes use of the solids hints already embedded in an object to identify it as a solid.



In some cases, the automatic detection method may not meet what you are trying to seek during creating your solids. For this, the manual method for creating solids gives you more control over solid creation.

Solid Creation Group

Auto Detect Solids:

In some cases, you may need to have more control over solids creation rather than using the automatic detect function. Here comes the role of the Creation Toolbar.

The Creation Toolbar displays two buttons to manually create and revert solids using the Graphical User Interface (GUI), as shown in the following image. This toolbar provides options to do or undo solid creation for the selected geometry(s) or solid(s), respectively. The two buttons are:




- **Single Solid:** Create Solid button allows you to manually create corresponding solids from the selected geometry or assembly. You can select a geometry or an assembly either using the Geometries Tree or from the 3D Area. You can also select multiple geometries from the Geometry Tree by holding the Ctrl key on the keyboard and clicking the desired , then pressing the Create Solid button in order to create the desired solid. After clicking the Create Solid button, only one solid will be created and all of its corresponding geometries will be disappeared from the Geometry Tree and moved to the Solids Tree.
- **Multiple Solid:** Revert Sold button gives the user the option to undo the creation of a solid(s), by simply choosing the desired solid(s) to be reverted from the Solids Tree, and then clicking the Revert Solid button. You can select a solid either using the Solids Tree or from the 3D Area. You can also select multiple solids from the Solids Tree by holding the Ctrl key on the keyboard, then pressing the Revert Solid button in order to revert the desired solids.


Appearance Group

Appearance:

Sometimes, you may want a certain object to inherit the movement of a specified solid without including it in the equations of motion used by the corresponding solver, here the Manipulation Toolbar comes in handy. You find only one button in the Manipulation Toolbar, as shown in the following image:




- Add Visuals: This button allows you to attach selected object elements to an existing solid as visualization object for the visualization purposes that do not included in the simulation's calculations. To add a visual, select the desired object(s) from the Geometry Tree, then click the Add Visuals button. Once it is clicked, the Select Solid dialog box (as shown in the following image) appears asking you to select the desired solid that you want to attach visuals to.



A solver is a component of SimLab Composer. SimLab Composer provides a library of solvers, each of which determines the time of the next simulation step and applies a numerical method to solve the set of equations that represent the model.



The Visual Icon appears  next to the visual object's name in the Solids Tree. You can toggle this icon to turn it back as a normal object combined within the solid.



Visual elements can be disabled or enabled in the Solids Tree only if the Solids Tab is activated.

Hide/ Show:

Hide/Show Toolbar is considered a handy and cool tool while working in simulation:

- **Hide:** It hides visible object(s) from the 3D Area.
- **Show:** It displays hidden object(s) in the 3D Area.






This tool makes your work easier, if you exploit it while creating solids in complex models.

Simulation Tree

Simulation Workbench Tree:

There are three kinds of tree views in the Simulation Workspace:


- Geometries Tree
- Solids Tree
- Links Tree



Geometries Tree

The Geometries Tree is a graphical control element that presents a hierarchical outline view of geometry items existing in the scene. Each geometry branch or node can have a number of subitems. This is often visualized by indentation in a list. A geometry can be expanded to reveal subitems, if any exist, and collapsed to hide subitems. The Geometries Tree allows the user to easily manage and navigate geometry objects.


As shown in the following image, the Geometries Tree is located at the left-side of the application window.



Solids Tree

The Solids Tree is a graphical control element that presents a hierarchical outline view of solid items created in the scene. Each solid branch or node can have a number of subitems. A solid can be expanded to reveal subitems, if any exist, and collapsed to hide subitems. The Solid Tree allows the user to easily manage and navigate among solids for selection or property modifications.


The Solids Tree is located at the right-side of the application window which is grouped with the Links Tree, the Solids Tree.



Links Tree


The Links Tree is a graphical control element that presents a list of created links connecting solids in the scene. The Links Tree allows the user to easily manage and navigate among solids for selection or setting properties.

The Solids Tree is located at the right-side of the application window which is grouped with the Solids Tree, as shown in the following image, the Links Tree.



Models Library

The Models Library acts as a container for pre-installed simulation models that come with the Simulation Edition of SimLab Composer, distributed into three groups: Basic Physics Experiments, General, and Collision (as shown in the following image). It is located at the bottom for the Solids workspace. You can choose any model of the provided sample just to run it as it is or edit it as you wish.



The toolbar of the Models Library is located vertically at its left-side, presenting the following three buttons:

- Add New Item: The Add New Item button allows the user to add new created simulation model to any activated model tab within the Models Library.
- Delete Item: This command discards the selected model from the panel of the activated tab.
- Manage Library: The Manage Library button launches the Manage Library dialog box to give the user options to create, delete and rename model groups which are presented by tabs.
- Download item: This task is the same as in the Material Panel described in Navigator Panel.
- Share Contents: This task is the same as in the Material Panel described in Navigator Panel.
- Change View: This task is the same as in the Material Panel described in Navigator Panel.



The Models Library is only associated with the Solids tab; it appears once the Solids tab is activated. By default, it also appears when you switch to the Simulation workbench.



As a start point, you can take a preview of what SimLab Simulation is capable of by start running the provided models.


Links Menu

In simulation, the behavior of a solid is governed by two things, the first is the total external forces affecting it, and the second is the link that defines the relationship between it and another different solid acts as constraint that are enforced by.

Using the Links Tool, you add joints, springs, forces, and torques to control the mechanism behavior. The Solids Tool contains the following Groups:

- Joints Group.
- Spring Group.
- Force/Torque Group.

Each of these toolbars is covered in the following sections.





Ground always exist in simulation although it isn't visible to the user.



The Lock Icon is different in simulation. Locking an object makes it invulnerable against any external force.



In SimLab Composer, every simulation case requires creating solids but creating Links is optional (it depends on the nature of the simulation). A Link defines the relationship of two solids to each other. Consider these prerequisites when you start every simulation project.




The simulation process is very conservative! Before you start building your simulation, make sure that you are satisfied with your model and you don't want to modify it outside of the Simulation Workbench.

Joints Group

Joints:

A joint is something like a hinge, which is used to connect two solids. It is a relationship that is enforced between two bodies so that they can only have certain positions and orientations relative to each other. To create a joint between two solids, you must choose the type of joint from the Joints Menu then the Joint Properties Panel will appear on the left-side.

Joints Group is the leftmost group on the Links menu. You find five buttons in this groups, as shown in the following image. A brief description of each joint type, supported by the SimLab Composer's simulation engine, is given as follows:



- **Fixed:** This type of joints maintains a fixed relative position and orientation between two solids. In practice, using this joint is rare. If you need two bodies to be glued together, it is better to represent them as a single solid when deciding that both of the solids hold the same properties during the simulation session.
- **Revolute:** A revolute joint (also called pin joint) is a one-degree-of-freedom kinematic pair used in mechanisms. Revolute joints provide single-axis rotation function used in many places such as door hinges, folding mechanisms, and other uni-axial rotation devices.
- **Prismatic:** A prismatic joint (also called slider) provides a linear sliding movement between two bodies. The two joined solids have their rotation held fixed relative to each other, and they can only move along a specified axis, chosen by the user while specifying the joint properties.
- **Spherical:** A spherical joint (also called a ball and socket joint) is a joint in which the ball-shaped surface of a solid fits into the cup-like indentation of another solid. This type of joint allows the solid to move in a 360 degree angle—with more freedom than other joints.
- **Cylindrical:** A cylindrical joint is a two-degrees-of-freedom kinematic pair used in mechanisms. Cylindrical joints provide single-axis sliding function as well as a single axis rotation, providing a way for two rigid bodies to translate and rotate freely.



Once you select a Joint, you have to set its properties in order to work appropriately.


Geometric Group

Geometric:

The Geometric groups concerns with shape, size, relative position of solids, and the properties of 3D space. To create a joint between two solids, you must choose the type of joint from the Joints group then the Joint Properties Panel will appear on the left-side.

considers questions of relative position or spatial relationship of geometric figures and shapes.

Geometric group is located on the Links menu. You find two button in this toolbar, as shown in the following image. A brief description of this button is given as follows:




- Distance : creates a link between two solids based on maintaining a certain distance between them at all times during the simulation.
- path: specify a path in the scene for the solid to follow during the simulation

Spring Group

Spring:

Spring: This button allows you to create a spring as a link between two solids. A spring is an elastic object used to store mechanical energy.




Once you click upon the Spring Button, you have to set its properties in order to work properly.

Force/Torque Group

Force/Torque:

In addition to joints and springs, you can affect the behavior of a certain solid by applying an external force or torque on it.


The Force/Torque group is located at the rightmost on the Links menu. You find the following two buttons in this groups, as shown in the following image:



- Force: This button allows you to apply an influence (push or pull) which tends to change the motion of an object including to begin moving from a state of rest, i.e. to accelerate. In other words, a force can cause an object with mass to change its velocity. A force has both magnitude and direction.
- Torque: This button allows you to apply an influence which produces changes in rotational speed of an object.

The Properties Panel of the Force/Torque appears at the left-side of the screen. Properties that are intersect by Force and Torque, as shown in the following image:

- Name: Where the user specifies a name for the new force or torque.
- Mode: This section allows the user to interchange between force and torque modes.
- Application Space: The user specifies whether the force or torque will follow the affected solid as it moves (Local), or stay static on the original point of application (World).
- Affected Solid: Where the user selects the affected solid.
- Location: Where the user selects the application point and axis for force or torque, in addition to that the ability to flip the force or torque direction.
- Magnitude Function: This edit button, if clicked, displays the Function Editor dialog box where the user specifies and selects the desired magnitude function for force or torque.



The Force/Torque Function Editor dialog box appears, when you click over the edit button of the Magnitude Function. This dialog box is shared by both of Force and Torque, it contains the following parameters:

- Motion Function: Constant, Ramp, 3-4-5 Polynomial, Polynomial, Sine, Derivative, Integration, or Sequence.
 - Constant.
 - Ramp: Initial Value and Slope.
 - 3-4-5 Polynomial: Amount of Displacement and Duration of Motion.
 - Polynomial: C0, C1, C2, C3, C4, and C5.
 - Sine: Amplitude, Phase, and Frequency.
 - Derivative: Choose Function.
 - Integration: Choose Function, Constant (C0), Lower Limit (X1), and Upper Limit (X2).
 - Sequence: Select Sequence.
- Function Plot: Start, End, Step, Plot Area, and Update button.




The Function Editor dialog box of Magnitude Function for Force and Torque is the same Function Editor dialog box of Motor Function for Prismatic and Revolute Joints.

Gears Group

Gears:

A Gear or Cogwheel is a rotating machine part having cut teeth, or cogs, which mesh with another toothed part to transmit torque, in most cases with teeth on the one gear being of identical shape, and often also with that shape on the other gear. To create a gear between two solids, you must choose the type of gear from the Gears group then the Gear Properties panel will appear on the left-side.

Gears group is located on the Links menu. You find two buttons in this groups, as shown in the following image. A brief description of each button, supported by the SimLab Composer's simulation engine, is given as follows:




- **Gear (Gear Train or Transmission):** Two or more gears working in a sequence. such gear arrangements can produce a mechanical advantage through a gear ratio and thus may be considered a simple machine. Geared devices can change the speed, torque, and direction of a power source. The most common situation is for a gear to mesh with another gear.
- **Rack and Pinion:** a gear can also mesh with a non-rotating toothed part, called a rack, thereby producing translation instead of rotation. A rack is a toothed bar or rod that can be thought of as a sector gear with an infinitely large radius of curvature. Torque can be converted to linear force by meshing a rack with a pinion: the pinion turns; the rack moves in a straight line. Such a mechanism is used in automobiles to convert the rotation of the steering wheel into the left-to-right motion of the tie rod(s). Racks also feature in the theory of gear geometry, where, for instance, the tooth shape of an interchangeable set of gears may be specified for the rack (infinite radius), and the tooth shapes for gears of particular actual radii are then derived from that. The rack and pinion gear type is employed in a rack railway.

Pulley Group

Pulley:

A pulley is a wheel on an axle or shaft that is designed to support movement and change of direction of a cable or belt along its circumference. Pulleys are used in a variety of ways to lift loads, apply forces, and to transmit power. To create a Pulley between two solids, you must choose the link type from the Pulley toolbar then the Pulley Properties panel will appear on the left-side.

Pulley tgroup is the rightmost group on the Links menu. You find only one button in this group, as shown in the following image. A brief description of the button, supported by the SimLab Composer's simulation engine, is given as follows:



- **Pulley:** A pulley may also be called a sheave or drum and may have a groove between two flanges around its circumference. The drive element of a pulley system can be a rope, cable, belt, or chain that runs over the pulley inside the groove.


Simulation Menu

After defining the required solids and their relationships that connect each other using joints, forces and torques, now you are ready to perform the simulation and see the results, this can be done after switching to the Simulation menu where simulation is controlled and executed.

After you finish setting up your project, switch to the Simulation menu where the simulation is controlled and executed. The Simulation menu contains the following groups, as shown in the following image:

- Start/Stop Menu.
- Parameters Menu.
- Collision Menu.
- Post Processing Menu.

Each of these toolbars is covered in the following sections.




Start/Stop Group

Start/Stop:

You can start or stop the run of a simulation by clicking over the Start/Stop button (as shown in the following image) .

- Start/Stop: This toggle button allows you to choose one from two predefined options (Start and Stop). The icon of which changes with each click and cycles between two states; the currently displayed value presents the next state.




Before you run the simulation, you may need to alter the default simulation setting to what fits the application of your project exercise (Simulation Parameters are discussed in the next section "Parameters Group").

Parameters Group

Parameters:


Often you need to change the simulation parameters before attempting to run a simulation or after stopping a simulation in order to configure the settings to what suits your requirements. The Parameters Group is located next to the Start/Stop Group. You find only one button in this group, as shown in the following image:

- Parameters: The Parameters button allows you to set up options related to the utilized solver and other various general and advanced options.



The Simulation Parameter dialog box appears when the Parameters button is clicked. This dialog box is a preference pane contains multiple panels, using tabs as a navigational widget for switching among three sets of settings. The three tabs are: General, Solver, and Advanced.


- The General Tab includes the following setting fields, as shown in the following image:



1. Time Step: This numerical field used by the chosen solver to determine the time step (in seconds) between iterations; reducing this value often produces more accurate results, but this requires executing additional calculations that affects the simulation speed and the size of the generated data. The default value is 0.001.
2. End time: This numerical field tells the selected solver at any time (in seconds) the simulation will be stopped. Its default value is 10.
3. Recording Simulation Results: This numerical field is used to ignore storing parts of the simulation data, and only saves data at a point after each interval specified (in time steps) by the user. It is usually used when the time step is very small, and the resulting data is very large. Its default value is 1.


4. Gravity: X, Y, and Z: Specify (in m/s^2 : meter per second squared) the gravitational acceleration in X, Y, and Z directions. The default values are 0, 0, -9.80, respectively.

- The Solver Tab includes the following setting fields, as shown in the following image:




1. Solver: Projected SOR, Multithreaded SOR, Projected SSOR, Projected Jacobi, Projected MINRES, Projected BB, Projected PCG, APGD, and DEM. (the default solver is Projected MINRES)
2. Integrator: Anitescu Stepper and Tasora Stepper (the default integrator is Tasora Stepper)
3. Maximum Number of Velocity Iteration: (the default value is 30)
4. Maximum Number of Stabilization Iteration: Only associated with the Tasora Stepper Integrator. (the default value is 10)
5. Penetration Recovery Speed Limit: Only associated with the Anitescu Stepper Integrator (in m/s: meter per second) (the default value is 0.6)
6. Young Modulus: Only associated with the DEM Solver, only enabled if the DEM Solver is chosen. (the default value is 200000)

- The Advanced Tab includes the following setting fields, as shown in the following image:



1. Overrelaxation Factor: This option is associated with the following solvers: Projected SOR, Multithreaded SOR, Projected SSOR, and Projected Jacobi. (the default value is 1)
2. Sharpness Factor: This option is associated with the following solvers: Projected SOR, Multithreaded SOR, Projected SSOR, and Projected Jacobi. (the default value is 1)
3. Minimum Bounce Speed: This option is associated with with all of the Solvers (in m/s: meter per second). (the default value is 0.15)
4. Use SimLab Advanced Collision System: (this checkbox is enabled by default)
5. Enable Sleeping: (this checkbox is disabled by default)

- The Visual Tab includes the following setting fields, as shown in the following image:




1. Hide helpers during simulation.

Collision Group

Collision:

You find only one button in the Collision group, as shown in the following image:



- Enable All: This toggle button allows you to choose one from two predefined options (Enable All and Disable All). The icon of which changes with each click and cycles between two states; the currently displayed value presents the state which will be applied if the the user clicked it. By default, collision is disabled.




SimLab Composer allows you to enable and disable each Solid individually by using the its independent Solid Properties Panel.

Post Processing Group

Post Processing:

The user can always benefit from the saved result of the most recent successful simulation, either in exporting it to animation or plotting its generated data on charts. The Post Processing group is located at the rightmost on the Simulation menu. You find only one button in this group, as shown in the following image:



- To Animation: The To Animation button automatically exports the simulation results of the latest simulation session as an animation in the Animation Workbench.
- Solid trace point: attaches a visual guide on a solid's surface, the trace point's movement can be analysed using plots to study the behavior of the solid at that point.



In order to review or edit the frames of your recorded animation, go to the Animation Timeline which you can find at the bottom of the Animation Workbench.




In order to plot your simulation data, go to the Charting Area, which you can find at the bottom of the Simulation Workbench.

Plotting Library

Plotting Library:

For the purpose of simulation data analysis and post processing, the user can use this graphical technique for representing a simulation data set as a graph, showing the relationship between two or more variables. The visual presentation of different functions is very useful for users who can quickly derive an understanding as a short path to gaining insight in terms of testing assumptions, model selection, relationship identification, factor effect determination, etc. as shown in the following image a Plotting Area of two graphs.

The panel of the Plotting Library is located vertically at its left-side, presenting the following four buttons:



- Add New Plot Tab: This button allows the user to add a new plot tab to Plotting Library.
- Delete Current Plot Tab: This button allows the user to delete the activated Plot Tab.
- Manage Library: The user can add multiple graphs assigned to present the desired simulation data. Four types of chart formation are available, as shown in the following image Single Plot, Dual Vertical Plots, Dual Horizontal Plots, and Four Plots.
- Manage Curves: This launches the Manage Curves dialog box (as shown in the following image) letting the user to plot selected channel(s) on the desired graph area.




The Plotting Area is only associated with the Simulation Tab; it appears at the bottom of the Simulation Workbench once the Simulation Tab is activated.

Interactive Menu

Simulation mode is developed for real-time Interactive Simulation. The new version of SimLab Composer takes Simulation to the next level, interactive simulation was added to allow the user to control machines using a Keyboard, or a Joystick.

Designed to work with Xbox One Controller, and possibility to work with other game controllers such as PS3 game controller.



TIP



Interactive Simulation supports pointer devices, sliders, keyboards, and joysticks.

Video



Tutorial for VR Interactive Simulation:




Interactive Simulation with SimLab VR Viewer


Start/Stop Group

Start/Stop:

You can start or stop the run of a interactive simulation by clicking over the Start/Stop button (as shown in the following image):



- **Start/Stop:** Either to start or stop Interactive Simulation.






Interactive Simulation supports pointer devices, sliders, keyboards, and joysticks.

Design Group


Design:

You find two buttons in the design group, as shown in the following image:



- **Design Panel:** A button that launches the Interactive Physics Entities dialog box.
- **Parameters:** A button that launches the Simulation Parameters dialog box.

- The Design Tab includes the following setting fields, as shown in the following image:




Plus: It is a button with green plus icon.

Minus: It is a button with green minus icon.

OK: To confirm and accept settings.

Cancel: To abort operation.

The interactive Simulation Parameter dialog box appears when the Parameters button is clicked. This dialog box is a preference pane contains multiple panels, using tabs as a navigational widget for switching among three sets of settings. The three tabs are: General, Solver, and Advanced.



The Simulation Parameters dialog box is the same as the Simulation Parameters dialog box found in the Simulation Tab except for the General tab.



Interactive Simulation supports pointer devices, sliders, keyboards, and joysticks.

Forward (Support Sliders, Keyboard, and Console Controller)

The Interactive mode for simulation supports game controllers in addition to the standard input peripherals.

The Xbox One Controller is the primary controller for Microsoft Xbox One console. The Xbox One Controller is powered by 2 AA batteries, however, the Micro USB port can be used to power the controller, instead of its wireless connectivity.



(the Microsoft Xbox One controller)

Also, the Sony PS3 Controller is the primary controller for Sony Playstation 3 console. The Sony Playstation Controller features an internal built-in battery, however, the USB mini-B to USB-A cable can be used to connect the controller to PC by wire instead of its independent Bluetooth connection.



(Sony Playstation controller)



SimLab Composer offers direct support for the controller of Microsoft xbox one. In the other hand, the controller of Sony PS3 requires a third-party software to work properly with SimLab Composer on PC. For more information, contact us at (support@simlab-soft.com)

Through GUI (Slider Bars)

Horizontal slider lets you set or adjust a value by moving an indicator. This control is a horizontal slider with a handle that can be moved right and left on a bar to select a value. The bar allows you to make adjustments to rotation or speed value throughout a range of pre-defined values. It allows you to alter the movement speed while being in the scene by decreasing it through dragging to the left (Slower) or increasing it through dragging to the opposite direction (Faster).




Controller sticks are sensitive. So take advantage of this property when designing a panel of increase and decrease keys for the interactive entities for controlling control functions

Automation Workbench

Introduction:

SimLab Composer allows using Java Scripts to automate processes, Java script automation is supported in two modes:

1. Command line (for batch processing for a large number of files)
2. Interactive mode (from inside the GUI of SimLab Composer)



Scripting is supporting in the Ultimate edition of SimLab Composer

Command line Java Scripts:

Java scripts can be run from the command line by using the following command

So if the user named the first script as example.js . And saved it in folder C:\Scripts, The user should use the following command

Passing arguments to Java Scripts:

Looking at the first example, the user defined on top of the java script the name of the file to be imported and the output image file.

For this script to work as expected, it is the users responsibility to name and place the input file as "c:\\temp\\input.obj" and to make sure the output file "c:\\temp\\output.png" is copied to another place before re-running the java script, so it is not overwritten.

Another option for the user is to use the input file name and the output image name as arguments as shown in the following scripting

To do this, instead of defining the variables on top of the script as done before, we can use the `runtime.args` functionality, as shown in the following example:

Other than changing the first two lines, the rest of the script is just the same.

To use the argument based script as before the user should use the following command:

This allows the user to control the import file and output image on the command line.

`runtime.args` supports the following argument types:

- String
- Number
- Color
- Vector 3
- String Array
- Number Array
- Color Array
- Vector 3 Array

My first Java Script:




The following script, imports a file, sets camera in a good position, and renders an image and saves it.


Interactive Scripting - Running Java script interactively

The user can run Java Scripts interactively in different ways:


1. Select a script from the scripting library, drag it, and drop it on the 3D area



2. Select a script from the library, then from the script menu, click Run



3. From Script menu, click new, type the Java Script code and then click Run



Using UI Elements In Interactive Mode:

Interactive Java scripts allows the user to create a dialog from the script to collect needed data, supported types include:


- DATA_TYPE_VALUE: value number
- DATA_TYPE_STRING: string
- DATA_TYPE_BOOL: boolean
- DATA_TYPE_VECTOR3: vecotr 3
- DATA_TYPE_RAY3: ray 3 (the user can enter the value or pick from the scene)
- DATA_TYPE_NODE: scene node (the user can enter name, or select from the scene) DATA_TYPE_NODE_ARRAY: array of scene nodes
- DATA_TYPE_COLOR: color
- DATA_TYPE_FILENAME_OPEN: open file name

- DATA_TYPE_FILENAME_SAVE: save file name

The user can simply create GUI to collect users data by using the following command:

This script will simply create a frame and allow the user to input values of First and Last frames

Values set by the user will be defined in data[0] and data[1].



The dialog above was created using the following script:

The user can set any number of inputs needed for the java script to run, this script is taking multiple objects (Nodes) and two directions which entered by user to copy these objects In two directions.




Find the all scripting commands for SimLab Composer online in this [page](#).

Debugging Java Scripts

Debugging

The integrated debugger in the interactive mode makes it easy for Java Script writer to follow the execution of the Java Script, and to check the values of variables, which makes creating new Java scripts faster, and fixing issues in existing ones easier.



Num

Description

1 Code Widget: The code widget shows the code of the currently selected script. The widget displays an arrow in the left margin, marking the code line that is being executed. Clicking in the margin of a line will cause a breakpoint to be toggled at that line. A breakpoint has to be set on a line that contains an actual statement in order to be useful. When an uncaught script exception occurs, the offending line will be shown with a red background.

2 Continue: Evaluation will resume normally.

Step Into: Evaluation will resume until the next statement is reached.

Step Over: Evaluation will resume until the next statement is reached; but if the current statement is a function call, the debugger will treat it as a single statement.

Step Out: Evaluation will resume until the current function exits and the next statement is reached.

Run to New Script: Run until the first statement of a new script is reached.

Run to Cursor: Run until the statement at the cursor is reached.

3 Scripts Widget: The scripts widget shows the scripts that are currently loaded in the script engine. Clicking on a script will cause its code to be shown in the code widget. When a script is no longer referenced by the debugger target it is removed from the scripts widget.

4 Breakpoints Widget: The breakpoints widget shows all the breakpoints that are set. A breakpoint can be disabled or enabled by clicking the checkbox next to the breakpoint's ID (the ID is provided so that the breakpoint can be manipulated through the console widget as well).

5 Console Widget: The console widget provides a command-line interface to the debugger's functionality, and also serves as an interactive script interpreter. The set of commands and their syntax is inspired by GDB, the GNU Debugger. Commands and script variables are auto-completed through the TAB key.

Debug Output Widget: The debug output widget shows messages generated by the print() script function. Scripts can use the special variables `__FILE__` and `__LINE__` to include the current location information in the messages.

Error Log Widget: The error log widget shows error messages that have been generated. All uncaught exceptions that occur in the engine will appear here.

6 Stack Widget: The stack widget shows a backtrace of the script execution state. Each row represents one frame in the stack. A row contains the frame index (0 being the inner-most frame), the name of the script function, and the location (file name and line number). To select a particular stack frame to inspect, click on its row.

7 Locals Widget: The locals widget shows the variables that are local to the currently selected stack frame; that is, the properties of the objects in the scope chain and the this-object. Objects can be expanded, so that their properties can be examined, recursively. Properties whose value has changed are shown in bold font.



For more info about Debugging Java Scripts please visit this [page](#)

Visual Scripting


Visual Scripting

Visual Scripting tool in SimLab Composer is a tool created to minimize the programming effort for non-technical users with no coding skills. Therefore, instead of writing the computer code in a text editor, the Visual Scripting tool allows the user to develop her/his desired programs via block diagrams using a graphical user interface. This makes the code easier to be written as well as to be understood: Any designer, artist or animator can read the diagrams easily and can quickly grasp the logic of the flow.

Getting Started

When you select the Visual Scripting tool from the automation workbench tools, the window will appear as shown in the figure below. It contains four main parts:

- 1) Options for 'Run' the existing flow, 'Create' a new flow, 'Open' or 'Save' flows.
- 2) The 'Main Object Groups Bar', which includes the category titles of all the available sources and functions.
- 3) For each 'Object Group', corresponding 'Sources' and 'Functions' are available.
- 4) The 'Work Space', where blocks can be dragged, dropped and linked to create the desired flow charts.



Any flow in Visual Scripting consists of three main components: Sources, Blocks and Connections.

A) Sources: Sources are used to define file paths and 3D nodes to be used as inputs for different blocks in the diagram. User can find several source types in the sources tab.


B) Blocks: Blocks are basically functions that can take inputs and produce outputs. Each block performs a single process. For example, the block in the left side in the previous figure takes an integer number as input and converts it to a string as an output. User can find several block types categorized into different tabs throughout the main bar.

C) Connections: Connections are used to make the whole flowchart meaningful by linking sources and blocks. Thus, they define which sources and blocks are connected. Accordingly, they arrange the execution order of the block diagram. The green ports on the blocks are not essential but they are very important to ensure the right execution order and to create dependencies between the blocks. To make the process easier for users, ports on each block are colored based on the data type that should be passed through them.

After completing the flow diagram, hit the run button to start the execution. A pop up message will appear once the execution is complete. Flowcharts can be saved and shared to be used in different projects.



In this video tutorial below you can learn how to using the Visual Scripting tool in the SimLab Composer 9.1.




You can visit the Visual Scripting web page in our website by this [link](#)

Running Flows from Command-line (with optional arguments)

The flows of SimLab Visual Scripting have the possibility to be executed from command -line interfaces, such as:

- CMD on Microsoft Windows.
- Terminal on macOS.

Optionally, data are passed as arguments through CLI to a flow in order to override particular sources' default values. To make flow's sources accessible from CLI, the user should do the following:

- 1) Open/create a flow with SimLab Visual Scripting.
- 2) Toggle CLI button  corresponding to desired sources.
- 3) Enter an identifier for the named argument key to be used in CLI.

[Command Syntax for Microsoft Windows]


```
SimLabComposer.exe {-fl <flow_file>} [ {-key1 <value1>} {-key2 <value2>} ]
```

[Command Syntax for macOS]

```
"/Applications/SimLab Composer 9.1.app/Contents/MacOS/SimLabComposer" {-fl <flow_file>} [ {-key1 <value1>} {-key2 <value2>} ]
```

or

```
open "/Applications/SimLab Composer 9.1.app/" --args {-fl <flow_file>} [ {-key1 <value1>} {-key2 <value2>} ]
```



In order to pass new width and length values to the above flow as arguments, the user needs to write in prompt a command-line similar to

```
SimLabComposer.exe -fl flowFile.simlabvs -length 10 -width 20
```



VR Workbench

A VR workbench, dedicated to Virtual Reality (VR), has been added to SimLab Composer as the sixth workbench.

The VR workbench contains the basic tools that are found in the scene building workbench along with the Animation workbench since those tools can prove useful in preparing your scene for Virtual Reality viewing.



Enrich your VR experience and add sound effects to everything (supported audio file format extensions are: .mp3, .wav, and .ogg).



In the video tutorial below teaches users how to show mechanical models in an interactive VR experience.

Simlab Composer

Mechanical Virtual Reality



Mechanical Training Series

Part 4


 SimlabSoft



[SimLab VR](#)

Visual Effects Menu

In the Visual effects menu, you will be able to create various dynamic visual elements that can further improve the realism in the VR experience.




Visual Effects Group

Visual Effects


This function has the supported visual effects types in SimLab Composer, which are suitable for VR workbench. Users can create two types of visual effects:

- **Create Web Browser:** Create an active web browser screen in your VR scenes and projects.
- **Create Fire:** Create fire from various presets and control its color and smoke for stunning visual effects in your VR scenes and projects.
- **Create Smoke:** Create smoke from various presets and control its color for stunning visual effects in your VR scenes and projects.

Create Web Browser:



This option allow the user to create the active web browser screen into the VR Viewer, when the user press on this option, a new object like a plane named "VR Web Browser" will appear into the 3D area and into the objects tree, select it and go to Properties dialog, under the VR Web Browser tab, add your web link into the URL field as shown in the image below, also the user can change the with and height the Web browser plane by using the white point on it.




Create Fire:

The fire effects let you create geometry that is camera-aligned. The objects always align to view default or connected camera. The plane geometry linked to the fire effects will rotate around the local Z axis to face the viewer. The fire effects are centered on the object (plane) which is linked to it.

To create Fire:

1. Go To visual effects menu » Click the Create fire button on it.
2. When setting the fire source for VR, the user has options for choosing the fire presets and choose (fire/smoke) color.



Fire is always kept aligned with the camera.




In object tree you will notice that the shape of the icon has changed to the fire shape.

Create Smoke:

The Smoke effects let you create geometry that is camera-aligned. The objects always align to view default or connected camera. The plane geometry linked to the smoke effects will rotate around the local Z axis to face the viewer. The smoke effects are centered on the object (plane) which is linked to it.

To create Smoke:

1. Go To visual effects menu » Click the Create smoke button on it.
2. When setting the smoke source for VR, the user has options for choosing the smoke presets and choose a smoke color.



In object tree you will notice that the shape of the icon has changed to the smoke shape.

Water Group

Make Water

Make a realistic water surface and configure its color, depth, and speed in your scenes and projects.


To Make Water:

1. Go To visual effects menu » Click the make water button on it.
2. Select 3d object to become water.
3. Go to launch viewer menu » Click Start Desktop Viewer.



In object tree you will notice that the shape of the icon has changed to the ground shape.


VR Water:



The water settings for VR workbench can be one of three options:

Water color: the user can select a color to use for the water.

Water Depth and Water Speed: These two parameters can be used to Make realistic water surface and configure its color, depth, and speed.




Remove Water

To Remove Water:

1. Go To visual effects menu » Click the remove water button on it.
2. Select 3d object to remove water.



After removing the water you notice that the shape of the icon has changed to its previous position.



Video Group


Make Video

With Make Video effects, image sequences can be set as Textures (or Labels) to animate device displays, The supported format at the moment is mp4.



To Make Video:

1. Go To **Visual Effects menu** » Click the **Make Video** button on it.
2. Select 3d object such as a screen to become a video.
3. Now go to VR Video tab from 3d object properties in the Right side and select your video in the Video File field, also you can set Play-On-Start, Interactive (play and pause when you click on the video in VR), loop and mute the sound, then start the VR Viewer.



4. Go to **View menu** » Click Start Desktop Viewer.

Remove Video

To Remove Video:

1. Go To **Visual Effects menu** » Click the **Remove Video** button on it.
2. Select 3d object to remove video.



Also the user can using the **Video Action** in order to make an objects controlling on the Video into the VR mode, for example the user can make the box object to pause, play, toggle, seek or play duration into VR, for more info about Video Actions in this section [SimLab Actions](#).

Ground (VR Only) Group

Ground:



Make object available for teleport.



Press and hold to activate Teleportation mode. Then Release to teleport to a valid destination.

A red teleportation pointer indicates possible teleportation on an object.

A green teleportation pointer indicates forbidden teleportation on an object.




Remove Ground

To Remove Ground:


1. Go To visual effects menu » Click the remove ground button on it.
2. Select 3d object to remove water.

Clipping Plane



Clipping Plane

Also known as Section Plane in VR, it can be static, animated, grabbable, and turned on/off dynamically.



Make Clippable Object(s)

Select objects to be clipped

Remove Clippable Object(s)

Select clippable objects to be removed




In the tutorial video below, you can show how make clipping plane.



Actions Menu



In the Actions menu, you can manage VR Docks and grabbable objects.



Docking Group

Make Dock and Target

Make dockable objects and interact with them in your scenes and projects.



Docking and target allows you to place moveable objects in a certain predefined manner upon interacting with them.



In object tree you will notice that the shape of the icon has changed to the Docking shape.



In object tree you will notice that the shape of the icon has changed to the target shape.

Remove Dock and Target

To remove the dock and a target:

1. Go To actions menu » Click the remove the dock and target button on it.
2. Select the object to remove dock and target.



The docking systems in Simlab Composer offer you a great method to interact with components in your design.




Creating VR dock and a target video tutorials:



Grabbing Group

Make Grabbable

Make grabbable objects and grab them in your scene and project.



- The green highlight object in an assembly refers to the current available part of the system that you can remove.
- The yellow highlight indicates that the object can be grabbed.
- You will also notice a blue highlight on the assembly indicating that you can place the object in there.

Interacting with assemblies in the SimLab VR viewer is very simple, the colored outlines and highlights will guide you throughout the assembly and dis-assembly process with ease and without any confusion.



Press "H" on your keyboard to toggle the hand. The hand has a fixed position at the center of the view, but can be moved away or towards you using the mouse scroll.




Creating VR assembly/disassembly instructions:





Grabbable Sequence


Grabbable sequence allow users to interaction with 3D objects in VR Viewer by linked these objects with animation sequence, In the image below, create animation rotation for the control arm and saved it as sequence, then linked this sequence to arm object used grabbable sequence tool, the arm can be picked up and control them up and down in VR Viewer.




To make grabbable sequence to object follow these steps:


1. In [VR Workbench](#), select **Actions** → **Make Grabbable Sequence**.
2. When The message below appear, select the object that want to make grabbable (create an [Animation Sequence](#) for it before) then click .



3. Now select the [Animation Sequence](#) for the object from [Sequence Library](#) then click .



4. Finally, Input scaling factor for object.



Press "H" on your keyboard to toggle the hand. The hand has a fixed position at the center of the view, but can be moved away or towards you using the mouse scroll.




Preview video for Grabbable Sequence.



Disassembly Group

Manage Assembly Process:

In the assembly management window you can graph and connect nodes based on the order you want them to be disassembled.




The assembly management interactions, settings:

- Green Plus button: Adds the selected node (in the 3d scene) to the disassembly diagram, if a disassembly graph node is selected, it will become the parent of the newly added node.
- Ladder button: Change parent of selected disassembly graph nodes, a graph node must be selected before clicking this button, the graph node selected afterwards will become the new parent - or - if a blank space is selected, the graph node will become independent (with no parent).
- Red Minus button: removes a node from the graph.
- Create new: create a new disassembly diagram.
- Rename: change the name of the disassembly diagram.
- Delete: remove the disassembly.



In the tutorial video below, you can show how used disassembled group.




Lists

Visualize Scene Options

Visualize scene options (scene states and animation sequences) by displaying them as entities in 3D world for easier and practical VR experiences.



Press "Alt" on your keyboard to show Pins, "LBUTTON" to select Scene States/Animation Sequences which appear as entities from the Pins.




Number


Description


- 1 A Trigger displays Pins if interacted by the user in SimLab VR Viewer. To add a Trigger select a Scene Node from Tree or from the 3D Area.
- 2 Remove a Trigger and eliminate any associated pins and scene options.
- 3 The list of Triggers.
- 4 Activate Scene States library to drag-and-drop Scene States into Pin nodes.
- 5 Activate Animation Sequences library to drag-and-drop Scene States into Pin nodes.
- 6 Add a Pin node to the current diagram, a Pin holds scene options chosen by the user. Once added, you can drag-and-drop either Scene States or Animation Sequences from their corresponding libraries to it.
- 7 Remove the selected Pin node from its diagram.
- 8 Watch an online video tutorial about how to visualize scene options.
- 9 (VR List) you can drag-and-drop Scene States/Animation Sequences here from their corresponding libraries.
- 10 Scene States/Animation Sequences.
- 11 List Properties, you can choose the shapes to display Scene States/Animation Sequences in VR Viewer.





• To create a Visualize Scene Options, Follow the steps below:


1. Open the SimLab Composer.
2. Before create a Lists, you must create multi [Scene States/Animation Sequence](#) (Create at least two).
3. When you finish the previous step, click **Actions** → **Visualize Scene Options**, the Visualize Scene Options dialog will appear.
4. **Select the object** which you want to make list for it Ex: Bedside Table, select the table model then **Add a Trigger** by click 
5. The object name (Bedside Table) should appear in the **Pin and Scene Options** side as shown in image below.



6. Now drag-and-drop Scene States/Animation Sequence (which created in step two) from [Scene States Library](#) into the VR List1  one by one.



7. The Scene States/Animation Sequence will appear under the VR List1  as shown in image below.







8. You can change the name of list and choose the shapes to display Scene States/Animation Sequences in VR Viewer from **List Properties** when

click 

Name:

Visual Presentation:

Shape to Apply on:    

9. When you finish, click  to save changes.



In the Video below, you can show how to Visualize Scene Options for VR and Mobile.


Tutorial



Events

VR Native Events

A state machine based system used for endless possibilities in your VR experiences, which includes location-based triggers.



- 1.** Create new Event.
- 2.** Copy the Event.
- 3.** Delete the Event.
- 4.** The list of Events.
- 5.** Edit Variables and Initial Values
- 6.** The Event Types:
 - When the object entered object.
 - When the object exited object.
 - When the scene state applied.
 - When the sequence ended.
 - When variable condition changed.
- 7.** Selection Node from Tree or from the 3D Area.
- 8.** Zoom to object.
- 9.** The list of Responses.
- 10.** Delete the Response.
- 11.** Copy the Response.
- 12.** Create new Response.
- 13.** The Response Types:
 - Change action for object.
 - Apply scene state.
 - Change variable value.
 - Play sequence
 - Play sound




VR Drumming Demo using events and response system.



Light & Shadow Baking

New technology that stores lighting and shadow information with objects separately and away from their materials. It means that user can change the material itself and/or modify its properties even change its texture without the need to re-bake it again and again.



The image below show you the difference between disable and enable light baking



Disable Light Baking



Enable Light Baking



Using Light baking for superior Mobile VR



The user can switch between the two to experience day and night views by use Sun light or interior IES lights in the VR scene.


Simlab Interior Series

VR LIGHTING




 SimlabSoft

360 Image



What is a 360 image?

A 360 or a panorama image, is a special type of image that allows the user to experience being inside a 3D scene, the user can view the scene on a mobile, or using Facebook or other viewers.



How to create a 360 image?

Creating a 360 image using SimLab Composer is very simple, first you need to create a VR camera, place it in the scene, then select the VR camera, and render a 360 image.



This process is shown in the following tutorial .



Sharing 360 images on facebook?

Facebook has one extra restriction on 360 images to be automatically detected, width to height ratio should be 2 to 1, for example if width is 2000, height on the image should be 1000

How to embed and use a 360 image in a website?

- Download photo-sphere-viewer JavaScript library.
- Added it in your website files.
- Embed the necessary JavaScript files needed such as: three.min.js, photo-sphere-viewer.js
- Add CSS:

```
html, body {
    margin: 0;
    width: 100%;
    height: 100%;
    overflow: hidden;
}
#container {
    width: 100%;
    height: 100%;
}
```

- In your body tag create container for 360 images:

```
<div style="color:#fff" id="container_pan"></div>
```

- Then Include JavaScript Code:

```
var div = document.getElementById('container_pan');
var PSV = new PhotoSphereViewer({
    panorama: '../Simlabimages/image360.jpg',
    container: div,
    time_anim: 3000,
    navbar: true,
    navbar_style: {backgroundColor: 'rgba(58, 67, 77, 0.7)'},
});
```

- Finally it will look like this :

```
<head>
  <title>Simlab 360 images</title>
  <link rel="stylesheet" href="../assets/css/360.css">
  <script src="../assets/js/Photo-Sphere-Viewer-master/three.min.js"></script>
  <script src="../assets/js/Photo-Sphere-Viewer-master/photo-sphere-viewer.js"></script>
</head>
<body>
  <div id="container_pan"></div>
  <script>
    var div = document.getElementById('container_pan');
    var PSV = new PhotoSphereViewer({
      panorama: '../Simlabimages/image360.jpg',
      container: div,
      time_anim: 3000,
      navbar: true,
      navbar_style: {
        backgroundColor: 'rgba(58, 67, 77, 0.7)'
      },
    });
  </script>
</body>
```

For more details and examples on how to embed a 360 image in a website visit these links: [Link 1](#), [Link 2](#)



[SimLab 360](#)

High dynamic range images (HDR) Creation

HDR (High dynamic range images) or environment images, is one of the preferred methods to light a 3D scene for rendering. Originally those images were generated using specialized cameras, or through specialized software, due to the processes involved in generating HDRs usually usually carry licenses preventing free distribution. SimLab Composer supports creating: 3D scene HDRs, Studio HDRs, HDR Studio, Created using SimLab Composer.



Generating HDRs with SimLab Composer:

SimLab Composer makes it easy to generate HDR images, with the freedom of distributing them as any other rendered image created using SimLab Composer, with the Composer 9.1, the user can create multiple 360 render image from the VR Viewer faster and easier without consuming the processor for the device.



View the following tutorial to learn how to create HDR images using SimLab Composer.



Sharing HDRs:

If you generated a special HDR that you want to share with SimLab Composer users, please send an email to support@simlab-soft.com and we will be glad to share it with the community.




[SimLab HDR](#)

Teleportation Points


Use Teleportation Points to navigate large scenes fastly by activating the X-ray view in SimLab VR/Desktop Viewer.



This is a guide showing the user how to use the different methods: 1. Walk through 2. Teleportation



360s Grid Technology



360s Grid Technology allow users to view the 360 images that have created and move among it in the VR Viewer



To use the 360s Grid Technology, Follow the steps below:

1. First you must create VR cameras and make a 360 renders from it, select Create VR Camera from 360 Image Menu and move the camera to properly location, doublecation the camera and add multiple cameras in the scene (At least two cameras).



From the output settings make sure the output ratio is two to one and the light specular depth is set to 100.


2. Now select the render **Multiple 360s** from **360 Image menu** to render 360 grid.

3. When the renders are finished, the render result will appear directly in the VR Camera Properties under (360 Section), in this section you can preview and change the 360 image, also can make the render appear behind the walls as move among the 360 images in the VR Viewer (it's Not Visible by default).



4. Now, select **Set 360 Start** from **360 Image menu** then select any 360 camera from 3d area to make it the first 360 image to be displayed at the start VR Viewer.

5. Finally, select **Desktop Mode** From **View**, the message below appear, select **360** then click **OK**.




360/Panorama Grid (How to create tutorial):



Viewer Menu


In the Visual effects menu, you will be able to create various dynamic visual elements that can further improve the realism in the VR experience.



SimLab VR Viewer Group


VR Viewer

In this part of VR workbench, you will find the "Viewer" menu, where you can export your design as a 3D-VR file format, or you can directly run the design either in Desktop or VR Mode. SimLab VR Viewer can be used by designers to share the VR experiences they create using SimLab Composer with their clients. This program is all what is needed for the end user to view VR experiences. The hardware setup of the end user is automatically detected, so the user can use HTC vive, Oculus rift is available, or the included desktop viewer.



• Show In VR Viewer


SimLab Composer comes with a special viewer that is developed to let users live and experience rich and interactive environments in two navigation modes; SimLab Composer gives the ability to export and navigate created VR projects in a special purpose viewer in Desktop Mode (i.e. Gaming controls using keyboard and mouse) and in VR Mode using modern VR peripherals.



You can now enjoy the greatness of SimLab VR/Desktop on Mac (macOS greater or equal to 10.12).

- **Add to Viewer**

This option allow user to export the scene as a *.VRpackage format then add it into her\his account in the [VR Viewer application](#) directly , when the user clicks on this option the dialog below will appear.



In this dialog above, the user needs to insert a title, publisher name, preview image (855x465), and description for the scene. This info will appear on the scene in the VR Viewer, also the user can protect the scene by selecting the 'Protected' option. (Protected files can be only viewed in SimLab VR Viewer, they can not be exported to other formats neither reopened by SimLab Composer).

- **Open Viewer**

User can open the [SimLab VR Viewer Application](#) directly in SimLab Composer by selecting this option.



In this video below we will show you how to use the VR Viewer in SimLab Composer.



[SimLab VR Viewer](#)


Navigation

Navigation in VR

* *Keyboard:*

You can use your computer's keyboard to move within prospect when paired with an HTC Vive. Here are the key mappings.

1- Arrows:



movement key:

1. Up arrow.
2. Down arrow.
3. Right arrow.
4. Left arrow.

2- Advanced Options:

- (H) Hide/show hand.
- (1) Default
- (2) Apply Scene Building Mode
- (3) Show Pins ([Lists](#))
- (4) View "Teleportation" points

- (5) Apply Measurement
- (space) Jump.

* Mouse:

Use your mouse to interact with objects in the VR world.



1- Left Mouse Button:

- Press and hold to show a selection pointer on screen and activate highlight mode for objects that have actions (such as, Scene States, Animation Sequences, Sound...etc) applied to them.
- While the selection pointer is pointing on an object that has an action, release to activate the action.
- Press and hold to grab the 'Grabbable' objects (in Scene Building mode).

2- Right Mouse Button:

- Single click to activate the highlight mode for the 'Grabbable' objects.

3- Scroll Wheel:

- Move your hand closer or further.
- By clicking middle-mouse button(Scroll Wheel), the GUI menu below will appear. In this menu, the user can find several useful options that allows him/her to build the VR scene such as, editing materials and environments, adding notes, inserting models and objects into the VR scene without going back and forth between SimLab Composer and SimLab VR Viewer again. The user can also save all changes directly from SimLab VR Viewer.



1

10

11

12

13

14

2

3

4

5

6

7

8


9

Material Editor

Plastic Metal Glass Emitter Water

Reflection 45%
Roughness 25%
Alpha 100%
Emission 0%

Captured Materials





1. Hide VR menu




2. [VR Catalog](#)




3. Material Editor: With the previous menu, the user can select any material from an object in SimLab VR Viewer by changing its color, material type (Plastic, Metal, glass, Emitter and water), with the useful basic settings into the VR Viewer. Also, He/she can pick materials from the scene and save them in the "Captured Materials" library using the "Eyedropper" tool. Moreover, he/she can apply the selected material from the library on any object by selecting "Paint Brush" icon then pressing on the designated object. Lastly, you can delete the material by pressing the "Red X" icon.




4. Environment Editor: This tool allows the user to make some adjustments and control the lighting of the environment for his/her scene. The following image, there are four options included in this menu: Sun and Sky, HDR, Fog and Advanced settings.




- Sun and Sky: In this option the user can enable/disable the sun and sky environment, and change between the day and night mode, also, he/she can edit sun and sky attribute values and the sun color inside SimLab VR Viewer.




- HDR: The user can enable/disable or even edit the light color and the brightness of the HDR through this menu.




- Fog: Is a technique used to enhance the perception of distance by shading distant objects differently, the user can enable/disable, change color, density and distance of the fog.



- Advanced Settings: The user can edit the intensity of Lights, such as, Spot lights and IES lights which he/she created it before importing it into the scene, also can change/choose the background to environment (HDR, Sun Light), single color or the image.




5. Navigation: There are three navigation modes inside SimLab VR Viewer: Walking, Flying and Mechanical mode.




- Walking Mode: This mode allows the user to walk around inside the scene in player's First-Person view, the speed of the walk can be increased by pressing and holding the Shift key while walking in the scene, also it can be decreased by pressing the "Caps Lock" key button for once and back to the normal speed by pressing it again.
- Flying Mode: The User can fly like a bird in the viewer.
- Mechanical Mode: This mode allows the user to turn the camera view around the center of the scene.



6. Notes: With this feature the user can create notes inside SimLab VR Viewer. This feature allows the user to place notes at any location in the scene and save its position for later visits. Also, the user can include some notes using the keyboard, marking the objects or recording voice memos.



- In the "Notes" menu below the user can change the image preview of any note by pressing the "Capture View" button. Moreover, you can press on "Pen" icon to start marking on objects and delete by holding right-click mouse button over it. Also, the user can Start/Stop recording his/her voice memos by pressing the recording button. Lastly, the user can delete his/her records or voice memos by pressing on the trash icon.



Recording Button





7. Help




8. **Save Scene:** This option allows the user to save scene changes in SimLab VR Viewer as a .VRpackage or .EXE file.



9. **Restart Scene:** This option allows the user to restart the VR Viewer in order to go back to the start point.



10. **Scene Building mode:** This dedicated mode enables the user to move, rotate, scale, copy, delete, and hide/show objects in SimLab VR Viewer.



- In this mode, the user can interact with VR scene elements using his/her two hands, also can grab objects as well.

If the user clicks on  in SimLab VR Viewer, these icons below will appear:



Hide/Show object.



Replace object with another object.



Rescale object to its default size.



Make a copy from the object or duplicate.



Delete the object.



To be able to interact with objects in Scene Building mode, object must be made as [Grabbable](#).




11. [Lists mode \(Visualized Scene Options\)](#)



12. Large Navigation mode: With this mode, the user can teleport among 360 cameras available inside the scene.



13. Apply Measurement mode: This mode allows the user to create and display the projected distance between 2 points in SimLab VR Viewer, the default unit is Meter. To use this mode, press and hold left-click mouse button and move over any object in the viewer, release the button when you are done.




14. Exit, Maximize/Restore Down and Minimize SimLab VR Viewer Screen.

Start Desktop Viewer

Start Desktop viewer

The Desktop Viewer is where you can examine the VR experience without having to use the VR Head mount display and controllers, each time you need to test the scene out, or in the case of not having a VR setup on the machine you are using.



You can now navigate through the scene in the Desktop viewer using the mouse and the keyboard, and you can assess the overall VR experience for further modifications and improvements.

What's new in VR Viewer

- Oculus Touch support
- New mechanical navigation mode
- AR




Press "escape" to exit SimLab viewer and go back to SimLab composer.

Start VR Viewer

Start VR viewer

The VR Viewer is where you can examine the VR experience with having to use the VR Head mount display and controllers, each time you need to test the scene out, or in the case of having a VR setup on the machine you are using.




Make sure that you are using HTC 5 (VR).

Vive Controllers

Vive Controllers:

Use the controllers to interact with objects in the VR world.





1- Trackpad:

- # Press and hold to activate Teleportation mode. Then Release to teleport to a valid destination.

Note:

- A red teleportation pointer indicates possible teleportation on an object.
- A green teleportation pointer indicates forbidden teleportation on an object.



2- System button:

- Fast press then release brings up the system main menu.

3- Tracking sensor:

- Move controller and intersect with objects to highlight grabbable objects in VR Viewer.
- Move controller to desired direction and pick a jump point.


4- Trigger:

- Press and hold to shoot a continuous beam and point it to a desired object in order to distinguish by highlighting if an object has action/action. Then Release, while the beam is still focused on a valid object, to activate actions such as Scene State, Animation Sequences, and Sound effects.



5- Grip button:

- Press and hold to enter grabbing mode and start grabbing valid objects.
- Fast press then release activates highlighting mode for grabbable objects in VR Viewer.




In the VR world, the two Vive controllers appear in different colors:

- a. Blue controller is the main controller (marked with a blue sphere as demonstrated in the image below).
- b. Green controller is the secondary controller.






Navigation tutorial for SimLab VR viewer video tutorial:



VR Viewer Application

VR Viewer Application


As another part of the SimLab VR framework for users, VR Viewer is an application that presents a professional way to store, manage, exhibit, share your VR scenes and projects with others.



Using SimLab VR Viewer allows user to see the list of available 3D models on the left side of the framework, after selecting the models the user can start desktop viewer or VR mode.




The user can access the online tutorial page by clicking on the image below on our website, for more tutorials: <http://simlab-soft.com/3d-products/simlab-composer-tutorials.aspx>.




Adding the scene on VR Viewer is very simple to do that, export the model you want to share from SimLab Composer as a (*VRzim,*VRpackage) file, then adding the model on the Viewer.

As you see in the image below, User can filter the models out of tags.



There are several elements that provide structure to how the commands are presented in the User-Interface, as shown below.





- Start Edit Mode: by clicking on this icon the user can add images, edit the title, the publisher and edit the description.
- Upload Package:
- Share Package:
- Pack Package: This function button display "Pack the Scene" dialog, in which the user can create (*.VRpackage) file based on the selected file format from the list.
- Delete Package: by clicking this icon the user can delete the package from the list.
- Edit Package Tags: by clicking this icon the user can remove or add tags.
- Help: by clicking this icon the user can access the online tutorial page.

Private Catalogs:

In the Free VR Viewer, users can now have two private catalogs, these catalogs contain the packages (up to 30 packages in each catalog for private and public) that the user has added to those catalogs And share them with specific friends and users as a viewer by adding their names and e-mail in the Viewer Management.



To create a private catalogs in Free VR Viewer, follow the steps below:

1. Open the Free VR Viewer by double clicking its desktop shortcut or from the start menu.
2. Press on  to login if you have an account, enter your email and password then press **Log in**, If you don't have account press  and enter your information and password then press **Register Now**.
3. In your account, select **Manage Catalogs** from the top right, the dialog below will appear.

The screenshot shows a software dialog box titled "John" with a close button (X) in the top right corner. It is divided into two main sections: "Catalog Management" and "Viewer Management".

Catalog Management:


- On the left, there is a list of catalogs. "Vehicles" is at the top, and "Architecture" is selected and highlighted in a dark grey box. Below the list are two orange buttons: "Add" and "Delete".
- On the right, under "Catalog Info", there are three input fields:
 - "Catalog Title:" with the text "Architecture".
 - "Catalog Tags:" with the text "house, tower, city, street,".
 - "Catalog Logo:" with the text "load/logo001.jpg" and a small orange button with three dots to its right. Below this is a small image of a city street.

Viewer Management:


- On the left, there is a list of viewers. "Adam Eagle" is selected and highlighted in a dark grey box, with "Bert Thin" listed below it. Below the list are two orange buttons: "Add" and "Delete".
- On the right, under "Viewer Info", there are three input fields:
 - "First Name:" with the text "Adam".
 - "Last Name:" with the text "Eagle".
 - "Email:" with the text "adameagle@yahoo.com".
- Below the input fields is a note: "Note: An invitation email will be sent to the given email address."

At the bottom of the dialog box, there are two orange buttons: "Save" and "Cancel".

4. In this dialog above, press **Add** from **Catalog Management** to create a new catalog, you can create two, enter the catalog information: catalog title, tags and logo image in the **Catalog Info** field.
5. In the **Viewer Info** field, You can add more than one user who can view the packages within this catalog, to add viewer press **Add** and enter the first name, last name and email for viewer, when you finish press **Save**.
6. Now the catalogs which have been created will appear in this menu below, press into any catalog and add the packages into it.



Check out VR Viewer cloud client video tutorials:





In this video tutorial below we will show you how to using the VR Viewer to share VR experiences with users on the cloud.




Set Start Position

Changeable Start Position:

In this part of VR workbench , the viewer start button will determine the starting location of your camera in the VR experience.

Click on " Start Position" to pick a starting location where you desire to start from in your scene and project. A human model is now loaded into the scene, this human will represent the Viewer during the VR experience.



To quickly position the viewer start, press "N" on your keyboard, then click on the ground to snap the Character to the desired location.




You can then rotate the character to determine the angle at which the viewer will start.

Export Group

Export

This function button will open the corresponding Export Geometry dialog. The export function enables the user to share the created 3D scene with others in different formats.

Clicking Export will display the Export Geometry dialog, where the user can share ZIM file with other , or to open it on the showroom.



VR/AR Mobile

VR/AR Mobile Viewer App

SimLab introduces a new and innovative mobile app for Android devices (iOS later) which allow user to live models and experiences exported from SimLab Showroom, also users can view any 360 degree (Panorama) images rendered by SimLab Composer or any third party.

Features of the mobile VR viewer:

- **3D Viewer support:** 3D View mode allows the user to view and share 3D models with others, The user can use finger gestures to rotate and zoom the scene
- **VR experience support:** VR mode allows using a mobile VR head set, to view 3D models in a VR experience.
- **Augmented Reality (AR):** The AR mode allows the user to place a 3D model in a real environment while maintaining the full 3D model interactivity.



Augmented Reality (AR) tutorial.



- **Light baking support:** To compensate for lower CPU power available on the mobile devices, without reducing output quality, SimLab VR Mobile viewer supports reading light baking results generated using SimLab Composer.




Using Light baking for superior Mobile VR



- To use our **SimLab AR/VR Viewer application on the mobile or tablet, following the steps below:**

a. Install the SimLab AR/VR Viewer application from play store, when the installer finish open the application, the screen below will appear.



1) In this menu user can:



Back to previous screen.



Exit from Application.



Go to application help.

- 2) 3D Viewer Mode
- 3) VR Viewer Mode with VR head set
- 4) Augmented Reality (AR) Mode
- 5) Add a new 3d model
- 6) 3D Model
- 7) 3D Model with 360 Grid Technology mark

b. To add a new model, you must export (.vrpackage) file into the Device, Google Drive or Dropbox, then press Add 3D Model and import the file.



When user import the model in the SimLab Application, it will appear automatically below its appropriate viewer mode, for example the models that support the 360 Grid Technology will not appear below the AR Mode.

c. Now, the model will appear in the screen, select the Viewer Mode at the top of the screen then Press on thumbnail of the scene to access it, Use White circles at the corners of the bottom to look around and interact in 3D Viewer Mode.



[SimLab Mobile Viewer](#)

Training Builder


VR Events Diagrams

VR training allow users to create an interactive environment inside the VR Viewer. It can integrate several inputs with built-in functions in order to generate desirable reactions. For example, when the VR viewer enters a specific area, an alarm sound plays or goes on. Inputs can take the form of a Scene State, an Animation Sequence, a Scene Object, or an Action. Functions include events and responses that are logically combined using the Boolean operations. For easier usability, functions are created using a diagram of smart blocks and connections that link the corresponding components together in a visual scripting manner.

Getting Started










When user selects the "Training Builder" option from the "VR Workbench" ribbon, a dialog box below appears, that contains the following options:













- 1) The current/selected Diagram.
- 2) Create a new diagram.
- 3) Edit Variables and initial values.
- 4) Remove selected diagram.
- 5) All needed Inputs, events and responses functions and Boolean operations.
- 6) Unlimited working area.
- 7) Help.









• For better understanding this system, it should be read as an "If-then statement". The User can add nodes, events, response functions and Boolean operations by clicking on them or by drag and drop into the working area. The connection lines define the information flow of inputs-blocks-events.

Icons	Inputs list
	Sequence
	Scene State
	Scene Node (object)
	String
	Variable
	Action
	Boolean
	Sound File


Icons	Events List
	If Scene Start
	If Scene State Applied
	If Sequence Ended
	If Node Entered Node
	If Node Exited Node
	If Node Triggered
	If Node Grab Started
	If Node Grab Ended
	If Delay


Icons	Responses List
	Then Apply Scene State
	Then Play Sequence
	Then Stop Sequence
	Then Glow Object
	Then Unglow Object
	Then Teleport to Camera
	Then Show Message Box
	Then Change Node Action
	Then Change Node Grabable State
	Then Change Variable Value
	Then Play Sound
	Then Video Action

Icons	Booleans List
	Variable Equals String State
	Objects Overlap State
	Object is Grabbed State
	And Operation
	Or Operation
	Not Operation




1. Let's make a simple exercise using the Training Builder. The main aim of this exercise is to run an alarm system (light and buzzer) when the user enters a specific area. To do so, we need to select the "Node Entered Node" from Events. Then we generate two nodes from the "Inputs" box: The first one is for the user, and the second is for the specific area.




2. Now select the user (viewer start position) from objects tree or directly from 3D area and press on this icon  to pick it up from the first node, and select the specific area (you can make a specific area by creating a box and make the Alpha value equals zero for its material) and drop it into the second node.




3. For connecting these two nodes together with "Node Entered Node" event just hold and press on the red point from first node and drop it in the "SceneNodeA" red point in "Node Entered Node" event as shown in the image, and the second node with the "SceneNodeB" red point as shown in the image below.



4. The two nodes are now connected with the "Node Entered Node" event as shown below.



5. Now we need to add two different responses function: "Play Sequence" to start the light animation (you need to create an [animation sequence](#) before) and "Play Sound" for buzzer, also add two inputs "Sequence" and "Sound File" to pick the light animation and the buzzer sound effect file on them, then connect these inputs block with response functions, and "Node Entered Node" event with these two response functions by the same way in the step 3.



- In edit variables and initial values dialog below, user can define infinite numbers of variables and get values for them, the variable values must begin with letters and can only contain letters, numbers and underscores. These variables can be used to maintain certain conditions such as, the status of doors and windows (closed/opened), garage (empty/busy), engine (working/not working) and so on. Then these variables can change with event functions inside the VR Viewer.

Edit Variables and Initial Values



Variable Name	Variable Initial Value
Door1_state	Opened
Door2_state	Closed
Door3_state	Closed
Garage1_state	Busy
Garage2_state	Empty
Light1_state	on
Light2_state	on
Light3_state	off
Window1_state	Open




The following video shows you an example for using VR Training Maker.



VR Catalog Menu

VR Catalog


With this feature the user can import ready models into the scene, such as tables, chairs, doors, trees and much more directly into the VR Viewer without need to go back to the Composer and run the viewer again. Also, she/he can add his/her own models into the Catalog and share them with others online.






To create the VR Catalog inside the SimLab Composer VR Viewer follow the steps below:

1. Save all the models you want as a (.vrpackage) format into the same folder on your device as shown in the screenshot below:



2. Create a preview image (PNG) for your catalog to display it into the catalog menu in the VR Viewer, We recommend to create a square image with size 256x256 px.

3. Go to the **VR workbench** select **Generate Catalog** from the **VR Catalog Menu**, the following dialog will appear:




4. In this dialog above, browse the folder which includes all the (.vrpackage) models which was created by step 1 as a **Source Folder**, and then browse the Preview Image (PNG) which was created in Step 2. Finally, enter the name for this catalog into the **Catalog Name field**, then press **Export**, a new file (.vrcatalog) will be created in the **Source Folder**.


5. Go to the **Environment Properties** by clicking on the environment text from the object tree.



6. In the **Environment Properties**, scroll down to the **Catalogs** section and select **Add From File** (The folder icon) then select the (.vrcatalog) file which was created in step 4 and press Open, the file location will appear in the image below.



Or you can upload the (.vrcatalog) file online on your website and add the URL link of it into the scene by pressing the green plus icon.



7. Now all the models will appear on the Catalog menu in the VR Viewer, with one click on the model you can insert it into the scene.

VR Catalog List

The user can add several catalogs into a list using **Generate Catalog List** from the **VR Catalog Menu**. The list will be exported as (.vrcataloglist) file, this file can be added and linked to VR scenes as the (.vrcatalog) file.



In this tutorial below we will show you how to create the VR catalog in the SimLab Composer 9.1.



You can visit the VR Catalog web page in our website by this [link](#).

Keyboard Shortcuts

Function	Shortcut
Create New Scene	[Ctrl] + [N]
Open Scene	[Ctrl] + [O]
Save Scene	[Ctrl] + [S]
Pack The Scene	[Ctrl] + [P]
Import Geometry	[Ctrl] + [I]
Export	[Ctrl] + [E]
Exit	[Ctrl] + [Q]
Undo	[Ctrl] + [Z]
Redo	[Ctrl] + [Y]
Make Instance	[Ctrl] + [T]
Create Copy	[Ctrl] + [C]
Show Scene Materials	[Ctrl] + [M]
Capture Camera Key Frame	[Ctrl] + [K]
Capture Scene State	[Ctrl] + [D]
Geometrical Info	[Ctrl] + [Shift] + [I]
Real Time View	F4
Render to File	F5
Select	Esc
Move 2D	1
Move 3D	2
Uniform Scale	3
Show Pivot	4
Capture From Selection	D
Freeze	F
Snap To Ground	G
Hide	H
Snap To Object	N

Pause Resume Render	P
Show	S
Unfreeze	U
Delete Del	Del
Top View	[Ctrl] + 1
Bottom View	[Ctrl] + 2
Front View	[Ctrl] + 3
Back View	[Ctrl] + 4
Right View	[Ctrl] + 5
Left View	[Ctrl] + 6
Default View	[Ctrl] + 7
Set Camera Target Vertex	C
Set Camera Target Into Selected Geometry Center	V
Fit All	[Ctrl] + [F]
Zoom To Object	[Ctrl] + [J]
Go To First Frame	Home
Play Animation	Space Bar
Go To Last Frame	End
Move to Previous Frame	-
Move 10 Frames Forward	Page Up
Move 10 Frames Backward	Page Down
Rubber Band Selection	Alt
XRay View	Alt + 1
Edges Only View	Alt + 2
Solid Illustration View	Alt + 3
Solid View	Alt + 4
Append To Current Selection	Alt + Ctrl
Remove From Current Selection	Alt + Shift

Contacts & Credits

Product Website:
<http://www.simlab-soft.com>

Support E-mail:
support@simlab-soft.com

To report any spelling mistakes, grammar mistakes or any errors, please contact us at info@simlab-soft.com

Copyright © 2019 Simulation Lab Software L.L.C. All rights reserved.
Product is available at <http://simlab-soft.com/3d-products/simlab-composer-trial.aspx>

Ordering and License

SimLab Composer is available in four editions: Educational/Hobbyist, Pro, Mechanical, and Ultimate. The Freeware edition does not need registering and is free to use for both commercial and non-commercial purposes. The Professional, Floating, and Educational editions have a trial period during which they can only be used for evaluation purposes. After this trial period, you must register the product or stop using it altogether.

You can instantly order any kind of the offered licenses for SimLab Composer at any time over the Internet with any major credit card, PayPal, purchase order, wire transfer, phone order, fax order, check or cash.

After you purchased a license, you'll receive your personal registration code and the release version of SimLab Composer.

Please visit <http://www.simlab-soft.com/3d-products/simlab-composer-buy.aspx> for pricing information.

Here's what you can do with paid license of our product:

- Remove watermark on the rendered images (depends on license type)
- Free minor version upgrades
- Free lifetime support. We promise prompt and courteous answers to your questions

Once you have ordered SimLab Composer registration key please enter it into the registration dialog box.

System Requirements

Hardware and software requirements for installing SimLab Composer are as follows:

PC:

- Intel or AMD processor
- Any graphics card with 256 MB or more (either dedicated or shared)
- 2 GB of RAM or more
- 2 GB of free hard disk space
- Monitor resolution of 1440 X 900 or greater
- Windows 64-bit (7.8 or 10)

Mac:

- Intel-based Mac, Core 2 Duo processor, or higher
- 2 GB of RAM or more
- 2 GB of free hard disk space
- Monitor resolution of 1440 X 900 or greater
- Mac OS X 10.9 or later

Feedback

If you have any comment/enquiry/feedback about our help please send it to us at: info@simlab-soft.com or support@simlab-soft.com

We would also appreciate if you fill our short survey about using SimLab Composer below:-

Thank you.